SL 50 1966

Invited talk to be presented at the Conference
on Applications of Thermoluminescence to
Geological Problems - Sponsored by the North
Atlantic Treaty Organization and U. S. Air
Force. Spoleto, Italy - September 5 - 16, 1966.

B7R 10569. 1
CONF-660919-3

CFSTI PRICES

H.C. \$ 1.00; MN .50

A Brief Survey of Radiation Effects Applicable to
Geology Problems*

By

Paul W. Levy

Brookhaven National Laboratory
Upton, N. Y., U. S. A.

MASTER

ABSTRACT

The effects of radiations on solids, i.e. radiation damage, is briefly reviewed with emphasis on the concepts that are applicable to geological problems. The difference between ionization and atom displacement processes is stressed. Topics included are: creation of defects by the different nuclear radiations, intrinsic defects, trapping and recombination centers, thermal untrapping and retrapping, and some qualitative aspects of the growth of radiation induced centers.

RELEASED FOR ANNOUNCEMENT
IN NUCLEAR SCIENCE ABSTRACTS

LEGAL NOTICE

This report was prepared as an account of Government sponsored work. Neither the United States, nor the Commission, nor any person acting on behalf of the Commission:

A. Makes any warranty or representation, expressed or implied, with respect to the accuracy, completeness, or usefulness of the information contained in this report, or that the use of any information, apparatus, method, or process disclosed in this report may not infringe privately owned rights; or

B. Assumes any liabilities with respect to the use of, or for damages resulting from the use of any information, apparatus, method, or process disclosed in this report.

As used in the above, "person acting on behalf of the Commission" includes any employee or contractor of the Commission, or employee of such contractor, to the extent that such employee or contractor of the Commission, or employee of such contractor prepares, disseminates, or provides access to, any information pursuant to his employment or contract with the Commission, or his employment with such contractor.

* Supported by the U. S. Atomic Energy Commission.

DISCLAIMER

This report was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government nor any agency Thereof, nor any of their employees, makes any warranty, express or implied, or assumes any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately owned rights. Reference herein to any specific commercial product, process, or service by trade name, trademark, manufacturer, or otherwise does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government or any agency thereof. The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States Government or any agency thereof.

DISCLAIMER

Portions of this document may be illegible in electronic image products. Images are produced from the best available original document.

Introduction

During the last two decades there has been considerable advance in "radiation damage" research. This name is commonly used to describe both pure and applied investigations on the effects of atomic and nuclear radiations on various substances. Obviously, the impetus for this effort is the necessity for finding suitable materials to use in reactors or in other intense radiation fields. The basic research in radiation effects has reached the point where there is a reasonably complete qualitative understanding of how radiation interacts with crystals. In particular, there is considerable understanding of the process which occurs when radiation creates defects in crystals. Also, it is understood how these defects affect the physical properties of irradiated substances, and how they are removed or annealed.¹

The radiations produced by accelerators, gamma-ray sources, X-ray machines, and reactors - except, in a sense, for the fast and slow neutron components - are indistinguishable from those emitted by the natural sources of radioactivity. The effects of natural α , β , and γ rays on minerals are the same as the effects that can now be produced in a controlled way in the laboratory. The principle difference is the great difference in radiation levels, or i.e., the rate of damage formation. Clearly, the results obtained from radiation damage research are applicable to the study of radiation effects produced by natural sources.

The following sections will very briefly summarize the present understanding of selected topics of radiation effects research and attempt to indicate a few experimental results that are applicable to geological problems.

The Difference Between Ionization and Displacement Effects

To begin, it is necessary to make a very clear differentiation between ionization effects and displacement effects. Ionization occurs when energetic charged particles pass through a substance. The electromagnetic interaction that exists between all charged particles imparts energy to any bound or free electrons in the bombarded substance. In non-metals, where the number of free electrons is negligible, bound electrons can be excited sufficiently to separate them from atoms and cause them to move through the crystal. These are ionization electrons. The "vacant state", or lack of an electron, from which the electron has been removed is a (electronic) hole and it also has mobility. In solid state physics language one says: ionization occurs when an electron is excited from the filled or valance band to the conduction band, creating a mobile electron in the conduction band and a mobile hole in the filled band. The important point is that ionization involves only electron and hole movement, not atom or nuclei movement.

When energetic particles pass through a solid they undergo elastic, and occasionally inelastic, collisions with the atoms in the material. When sufficient energy is transferred during the collision the struck atom or recoil atom is ejected from its normal lattice position. If the energy transfer is large enough it moves through the material until it comes to rest. Often it becomes lodged between other atoms, i.e., it becomes an interstitial. Its original site, now lacking an atom, becomes a vacancy. The important thing about this atom displacement process is that atoms are moved. Ionization can occur during the displacement process but atoms are not (there are very few exceptions) displaced because of the ionization process.

Defect Formation or Displacement Processes

Each of the different nuclear radiations produces defects in a characteristic manner. The number of defects created by the more common radiations are listed in Table I. The defect formation process associated with each type of radiation is briefly summarized below.

Alpha particles.

A majority of the defects created by natural radioactive impurities in minerals result from alpha particle emission. As the alpha particle passes through a crystal lattice, it gives up energy in the following way. It creates ionization electrons and holes, it displaces atoms from the lattice, and excites the lattice thermally.

Beta particles.

Energetic beta particles lose energy by ionization and by elastic collisions with lattice atoms. If sufficient energy is transferred in an inelastic collision to a lattice atom, it, the struck atom, will be ejected from its normal lattice position. The minimum energy that must be transferred to create a displacement is approximately 25 eV. A given beta particle will displace an atom only when the displacement collision occurs before it is degraded by ionization below the threshold energy. The minimum beta particle or electron energies required to displace boron, oxygen, or silicon atoms are 0.11, 0.16, 0.26 MeV respectively.

Gamma-ray photons.

Energetic gamma rays can also create defects. However, a two step process occurs. First, the gamma ray must produce a photoelectric or a Compton electron. Once this electron is formed it is indistinguishable from electrons produced in any other way and will create defects exactly as described in the section on beta particles.

Fast neutrons.

The formation of defects by fast neutrons is included here since neutron bombardments have been utilized in most radiation damage studies. This is another two step process. The first step is an elastic, or rarely an inelastic, collision between the impinging neutron and a lattice atom. If sufficient energy is transferred to the recoiling atom it is ejected from its lattice site and literally plows through the lattice. It gives up energy by ionization, by thermal excitation, and by knocking additional atoms out of their lattice sites. For example, a one MeV neutron can transfer sufficient energy to a single lattice atom for it to produce several hundred additional defects. Fast neutrons are produced by (α, n) reactions. Thus, in minerals fast neutron damage occurs, but only very rarely.

Fission Fragments.

The defects produced by fission fragments are formed by the same process described above for recoiling lattice atoms. However, because of its greater mass, each fragment creates several thousand displacements. Since the fission fragment range is very short this damage is highly concentrated.

Cosmic Rays.

The creation of defects by cosmic rays can occur in several somewhat different ways. The most likely process is the formation of "few prong stars". The incident particle, assuming it has energy in excess of 10 or 15 MeV, is captured by an atomic nucleus which becomes highly excited. It quickly disintegrates with the ejection of several fragments which will include some of the following: neutrons, protons, gamma rays, alpha particles, and heavier fragments. Each of these will create defects by processes which are the same or similar to those described above.

Additional Sources of Defects.

Most crystals contain defects in addition to those formed by radiation. Usually, these are incorporated into the crystal when it is grown. Impurities, which can properly be classified as a type of defect, are most often introduced during growth or solidification. They may be incorporated as interstitial atoms or they may occupy lattice positions, i.e., become substitutional impurities. Lattice defects, particularly vacancies, are also created during growth. This is especially so for crystals which crystallize from the melt. It is well known, from thermodynamic considerations, that cooling a crystal rapidly from near the melting point will "freeze in" the vacancy concentration that exists near the melting point.

Other processes will increase the concentration of crystal defects. There is a large amount of evidence showing that the defect concentration in metals is increased by subjecting them to plastic strain. These defects result from dislocation motion. There is less evidence for strain produced defects in non-metals but it is certain that this process occurs in the laboratory and in nature. Also, the recrystallization which occurs after crystals are initially formed can introduce additional defects. This should be an important source of defects in crystals that originally grew from solution and were subsequently subjected to heat and pressure. Recently, it was shown that high energy protons will react chemically with a substance under bombardment.² OH bands, which could be observed with an infra-red spectrophotometer, were formed in a soda-lime-silicate glass when it was irradiated with one MeV protons. This can be regarded as an additional source of crystal defects.

Ionization and Charge Trapping.

Ionization creates mobile electrons and holes that randomly move about in a solid. When the source of ionization is removed or "turned off" the distribution of electrons and holes can be considerably different than it was previously. The principle processes which occur during and after ionization will be described below. First, as mentioned above, ionization creates mobile electrons and holes. In most non-metallic crystals the holes have the shortest lifetime and are quickly captured or trapped by defects called, obviously, hole traps. Electrons usually have a longer lifetime and one fraction of those produced during the ionizing event are "permanently" trapped by defects which operate as thermally stable electron traps. The remaining fraction undergoes recombination. This occurs at recombination centers which are hole traps having the following important property. Namely, once they have captured a hole they have a high probability of capturing free or mobile electrons. The electron and hole neutralize one another and the recombination center, or more explicitly the defect which operates as a recombination center, is available to enter into subsequent recombination processes. There is an important consequence of this. The concentration of recombination centers remains substantially constant in any crystal. Also, the number of recombination centers available for recombination is relatively insensitive to the ionization level, particularly at low ionization levels. It is possible that the defects which operate as recombination centers are created, e.g., by radiation damage, or destroyed, e.g., by heat treatment. Recombination also occurs to electrons or holes in thermally stable traps. For example, a trapped electron may recombine with a hole formed during an ionization event occurring at a later time. The trap then becomes available for subsequent electron trapping.

The term "thermally stable" or "permanent" trap, used above will be defined explicitly below. Consider the concentration of trapped charge

in a crystal with a single type of trap of which all are completely empty when the ionization is "turned on". This could occur in nature when molten rock, containing radioactive impurity, suddenly solidifies and forms a defect which operates as a charged trap. If the ionization rate, from the natural radioactivity, is low the trapped charge concentration will increase linearly. This, and the cases where the ionization rate is higher, can be described mathematically.³ It is shown qualitatively in Fig. 1. If the concentration of recombination centers is comparable to the concentration of trapping centers the trapping rate will depend almost entirely on the recombination center concentration. The importance of recombination in the retrapping process is the subject of the next section.

Thermal Stability and the Retention of Trapped Charge.

The amount of trapped charge retained in a crystal over an extended period of time will depend on several factors. The most important of these are thermal untrapping and the retrapping of the thermally released charges. The untrapping of a charge due to thermally activated processes is given by the familiar expression:

$$\frac{dn}{dt} = n s e^{-E/kT} = n L \quad (1)$$

where n is the concentration of trapped charge, t is the time, s is the "attempt to escape" frequency, E is the activation energy and T is the temperature in $^{\circ}\text{K}$. A thermally stable trap is one for which $dn/dt = n L$ is negligibly small during a specified period, for example, during the time that all of the events created by the passage of an alpha particle are taking place, or, to give another extreme, a period of 10^6 years.

Retrapping is also a familiar process. If a crystal contains a large number of traps, and only a fraction of them are filled there is a high

probability that a thermal released charge will find its way to an empty trap. However, there is a finite probability that the untrapped charge will undergo recombination and be lost. The probability of retrapping in the simplest possible case is given by the expression

$$\frac{N - n}{N - n + R} \quad (2)$$

where N is the concentration of traps, i.e., filled plus unfilled, n is the concentration of trapped charge, and R is the concentration of recombination centers. Then $N - n$ is the concentration of empty centers. The total number of centers which can capture an untrapped electron is $N - n + R$. Thus, the probability of retrapping is just $(N - n)/(N - n + R)$. Actually, we should write that the probability of retrapping is $\sigma_N (N - n) / [\sigma_N (N - n) + \sigma_R R]$ where σ_N and σ_R are the cross sections for trapping and recombination, respectively. However, to retain simplicity we will put all cross sections equal to unity. Then in a crystal where retrapping is occurring the differential equation for the trapped charge concentration is

$$\begin{aligned} \frac{dn}{dt} &= - (\text{number thermally released}) + (\text{number retrapped}) \\ &= - nL + \frac{N - n}{N - n + R} nL = - \frac{nRL}{N - n + R} \end{aligned} \quad (3)$$

The solution of this equation, where n_0 is the concentration of trapped charge when t is equal to zero, is

$$n = n_0 e^{-\frac{n_0 - n}{N + R}} e^{-\frac{RLt}{N + R}} \quad (4)$$

The effect of recombination, i.e., the value of N computed from this equation for various values of the recombination term R , is shown in Fig. 2. When R is very large every thermally released electron is lost by recombination. In this case equation (4) reduces to equation (1), i.e., the trapped charge concentration depends entirely on the thermal untrapping process.

The physical process described by equation (4) is proceeding at a very low rate. This is especially apparent after examining Fig. 2. Thus, it is important to ask if equation (4) actually describes the trapped charge concentration. Is it possible that other processes predominate and the one described above is negligible? A large number of such processes are conceivable. For example, untrapping may result from vacancy or interstitial migration. Another possibility is plastic deformation which is known to cause untrapping under laboratory conditions. It is interesting to point out that these other untrapping mechanisms can be unimportant when retrapping is very efficient, or, i.e., when recombination is negligible.

Radiation Induced Traps and Recombination Centers.

In a mineral containing, or exposed to, natural radioactivity all of the processes described above will be taking place. Actually, additional processes which we have not discussed can be important. All of these processes and their various combinations can be described mathematically if it becomes necessary. To illustrate these we will give qualitative descriptions of a few more important cases involving both defect or trap formation and the subsequent trapping of charges in these traps. The upper part of Fig. 3 illustrates three situations regarding defects: I) a defect not initially present but produced by radiation, II) a defect initially present and not produced by radiation, and III) a defect initially present and increased by radiation. The lower part of Fig. 3 indicates one case, of many possible

cases, of the trapping of charges by all these defects as a function of time. For example, curve III could represent a vacancy in a crystal which becomes a color center by trapping an electron. Then curve iii would show the growth of this color center as a function of time. Curve II could represent a substitutional impurity that operates as a recombination center. In this case curve ii would saturate at a much lower concentration than shown. Innumerable additional examples could be given.

Measurement of Defects and Defects Containing Trapped Charges.

It would be exceedingly useful to be able to measure in any sample both the defect concentration and the fraction of defects which have trapped charges. Unfortunately, existing methods for making these measurements are, in almost every case, both indirect and difficult to perform. Some of the obvious methods are contained in Tables II and III. These tables are included, not to suggest that all of the methods are useful, but to stimulate the search for methods of defect measurement that can be applied to minerals.

There are distinct advantages in measuring defects or trapped charges by direct methods. Color center and esr intensity measurements depend directly on the number of trapped charges. In contrast, thermoluminescent measurements are a good example of an indirect determination. To relate the height of the glow peak to charge density requires a knowledge of the thermal release kinetics, the retrapping, and the recombination mechanisms. In principle, these can all be determined experimentally. However, the direct measurements are inherently both simpler and more accurate.

An Ideal Radiation Experiment.

If it is assumed that a suitable means is available for measuring defects or charged defect concentrations, such as esr signal intensity, or color center concentration,⁴ numerous useful experiments can be devised. We will give

an example of one possible experiment. Namely, the determination of the age of a mineral containing natural radioactive impurity. Actually, this example closely resembles experiments that have been performed using thermoluminescent calcite.

When the hypothetical sample is initially measured it is found that there are two signals. The intensity of these signals are measured and then the sample is exposed to a known dose of Co^{60} gamma-ray irradiation. After irradiation the signals are measured again and it is found that both are increased. This procedure is repeated. After several measurements, when the data is plotted, it is found to resemble Fig. 4. First, it is found that the lowest points fall on straight lines. Second, the extrapolation of these lines intersect on the zero signal ordinate. If it is assumed that the two signals are due to charges trapped on defects that were completely empty when the sample was formed, and it is also assumed that the trapped charge increases linearly with dose, then the difference between the points (1) and (2) is the dose received by the sample before it was originally measured. The natural radioactivity in the sample can be measured by well known chemical or counting techniques. And from the radioactivity content one can compute the natural dose rate. In some instances it can actually be measured. It is then necessary to assume that the signal is linear with dose to compute the age of the sample.

Actually, two additional assumptions are implicit in this procedure. First, the trap must be thermally stable. This can be ascertained experimentally by performing heat treatment experiments. If it is not thermally stable and retrapping occurs in the sample, the dose-signal-time relation can, in principle, be determined experimentally. The second implicit assumption is that the linear dose-signal relation is independent of dose rate or

irradiation time. Again, this relation may be tested experimentally and if it is not obeyed, in principle, corrections can be made.

Radiation Effects in Metals.

Mineral specimens that are entirely metal are relatively rare. Copper crystals and iron meteorites are two of the more common ones. When exposed to radiations the electrical resistance of metals is increased. These resistance changes are relatively easy to measure. (Actually, even larger resistance changes could be obtained by measuring the resistance at liquid helium temperature.) When the irradiated metal is heated the radiation induced resistance change gradually reduces as the temperature is raised. In this way a curve of resistance increment versus annealing temperature is obtained which decreases monotonically with temperature. The shape of this curve is very nearly independent of dose, but the ordinate, at any temperature, is given by a factor that is proportional to dose. If an irradiated sample is heated to a given temperature, T_1 , the resistance versus temperature curve described above is followed up to temperature T_1 . When the temperature is lowered the resistance remains at the value it had at T_1 . When the temperature is again raised the resistance remains at the same constant value until the original temperature T_1 is reached. Above T_1 it decreases, i.e., it follows the temperature-resistance curve originally described. When the sample is heated to a value $T_2 > T_1$ the same result is obtained. This procedure may be repeated in as many steps as one might desire until all of the induced increment is removed.

If it is suspected that a sample, e.g., a meteorite, contains a radiation induced resistance change, in principle, this can be determined in the following way. A curve of resistance versus temperature is obtained. The sample is then irradiated, e.g. in a reactor, and a second resistance

versus temperature curve measured. If the artificially induced resistance changes are similar to those in the sample, then one can estimate both the dose producing the original resistance increment and the maximum temperature the meteorite had been subjected to.

TABLE I.

Displaced Atoms Produced in "Thick" Materials with $Z \lesssim 30$ by Each Incident Particle or Gamma Ray

Radiation	Energy, MeV	Displacements	
		Theoretically Predicted	Measured - Stable at Room Temp.
α	0-5	50 - 200	30 - 100
β	0-5	2×10^{-2} - 2×10^{-1}	10^{-2} - 10^{-1}
γ	0-3	2×10^{-3}	10^{-3}
n	0-5	400 - 800	40 - 200
fission fragment	80	10^3 - 10^4	
cosmic-rays	>10	50-200 for each 5 MeV > 10 MeV	

TABLE II.

Some Methods of Measuring Charges Trapped on Defects

Thermoluminescence	
Electron Spin Resonance (esr or epr)	Direct Measurement - Crystals can be opaque - Certain impur- ities, e.g. Mn and rare earths can interfere.
Color centers	Direct Measurement - Requires transparent crystals.
Chemical	Valance change, radiolysis prod- ucts chemically separated.
Thermal charge release	Difficult to relate to total trapped charge
Photoconductivity	Difficult to relate to total trapped charge

TABLE III.

Some Methods of Measuring Defects

Thermoluminescence	Sensitive	}	To measure defect concentrations it is necessary to know the fraction of defects that contain trapped charge.
Electron Spin Resonance (esr or epr)	Sensitive		
color centers	Sensitive		
density	Not sensitive to small defect concentrations.		
refractive index	Not sensitive to small defect concentrations.		
rotary power	Not sensitive to small defect concentrations.		
lattice parameter change	Not sensitive to small defect concentrations.		
long wavelength neutron scattering	Not sensitive to small defect concentrations.		
low temperature thermal conductivity			
track counting	Optical and electron microscopes can be used.		
elastic constant and internal friction	Mechanical and ultrasonic methods, the latter could be sensitive.		
electrical resistivity	Metals only, but could be very sensitive.		

References

1. Detailed accounts of almost all aspects of radiation damage are contained in one or more of the following books:

Radiations Effects in Solids, G. J. Dienes and G. H. Vineyard, Interscience, New York (1957).

Radiation Damage in Solids, D. S. Billington and J. H. Crawford, Princeton Univ. Press Princeton (1961).

Radiation Damage in Crystals, L. T. Chadderton, Methuen, London (1965).

The Interaction of Radiation with Solids, Editors R. Strumane, et. al., North Holland, Amsterdam (1964).
2. "Proton Induced Hydroxyl Formation on the Lunar Surface", E. J. Zeller; L. B. Ronca, and P. W. Levy, J. Geophysical Research, (accepted - Vol. and page to be added in proof).
3. The following article, giving the equations that describe the coloring of glass, is directly applicable to minerals. "The Kinetics of Gamma-ray Induced Coloring of Glass", P. W. Levy, J. Amer. Cer. Soc. 43, 389 (1960).
4. "Use of Color Centers for Detection and Measurement of Defects", P. W. Levy, Symposium on Chemical and Physical Effects of High-Energy Radiation on Inorganic Substances, American Society for Testing and Materials, Philadelphia (1964), pg. 3.

Figure Captions

- Fig. 1. The trapped charge concentration, in a material containing a fixed trap or defect concentration, for different intensities of ionizing radiation.
- Fig. 2. The decay of the trapped charge concentration in a material where thermal untrapping, retrapping, and recombination are all occurring. The $R = \infty$ curve corresponds to the case where the trapped charge concentration depends only on the thermal untrapping rate. The concentration of recombination centers is so high every charge released undergoes recombination.
- Fig. 3. Defect or trap concentration and the trapped charged concentration i, ii, and iii, in a material subjected to both ionizing and defect producing radiation. Three cases are shown: I) the trap initially absent but produced by radiation. II) the trap initially present and unaffected by radiation. III) the trap initially present and increased by radiation.
- Fig. 4. Signal intensity versus dose in an experiment to determine the trapped charge in a mineral. This material would have to have two relatively empty traps when measurements were started. For this determination to be meaningful it would be essential to determine, e.g., by annealing experiments, that the trapped charges were almost completely stable at the highest temperature reached by the sample in the time it acquired the "prior dose".

Fig. 1

Fig. 2

DEFECT CONCENTRATION

TRAPPED CHARGE CONCENTRATION

Fig. 3

Fig. 4