EGG-CODP-10273

Ximconv User's Guide

Version 1.0.1

EGG-CODP--10273

DE92 018041

Fred R. McClurg

June 1992

**Idaho National Engineering Laboratory
EG&G Idaho, Inc.
Idaho Falls, Idaho 83415**

Prepared for the
U.S. Department of Energy
Under DOE Idaho Field Office
Contract DE-AC07-76ID01570

MASTER *ds*

DISTRIBUTION OF THIS DOCUMENT IS UNLIMITED

Abstract

This user's guide is the documentation for **ximconv**: a motif interface to the Image Tools developed by the San Diego Supercomputer Center (SDSC). The **ximconv** utility offers the user a point and click interface for converting from one file format to another.

Acknowledgments

The author would like to express his appreciation to the following:

Technical Services, Visualization and Imaging Team
Scientific Systems, Scientific Workstation Application and Administration Unit

Table of Contents

Abstract	iii
Acknowledgments	iv
Table of Contents	v
List of Figures	vii
List of Tables	viii
 Ximconv User's Guide	 1
1 Introduction	1
1.1 What is ximconv?	1
1.2 Is ximconv available?	1
1.3 What is needed to compile and execute?	1
1.3.1 How can I get a copy?	3
1.3.2 How do I compile the source?	4
1.3.3 How do I install the program?	4
1.3.4 How do I execute ximconv?	5
1.3.5 What if something goes wrong?	5
1.4 How does ximconv work?	5
1.5 How many file formats does it handle?	7
2 Using ximconv	8
2.1 Keyboard Shortcuts	8
2.1.1 KeyBoard Accelerators	8
2.1.2 KeyBoard Mnemonics	8
2.2 Customizing ximconv	9
2.2.1 Command Line Options	9
2.2.2 Application Defaults Options	9
3 ximconv Main Window	10
3.1 File Pulldown Menu (Meta+F)	10
3.1.1 Input File... (Ctrl+I)	10
3.1.2 Output File... (Ctrl+O)	12
3.1.3 Exit (Ctrl+X)	13
3.2 Options Pulldown Menu (Meta+O)	13
3.2.1 Feedback	13
3.2.2 Register	13

3.2.3	<u>V</u> erbose	14
3.3	<u>H</u> elp Pulldown Menu (Meta+H)	14
3.3.1	On <u>V</u> ersion...	14
3.3.1.1	On Version <u>x</u> imconv	15
3.3.1.2	On Version <u>i</u> mconv	15
3.3.2	On imconv <u>A</u> rguments...	16
3.3.2.1	On imconv Arguments <u>S</u> hort Help	16
3.3.2.2	On imconv Arguments <u>F</u> ull Help	17
3.3.3	On Input File <u>T</u> ype	17
3.3.4	On Specific <u>F</u> ormats...	17
3.4	Input Format Menu Option	17
3.5	Output Format Menu Option	18
3.6	Channel Depth Menu Option	19
3.7	Channel/Pixel Menu Option	20
3.8	Output Compression Menu Option	20
3.9	Interleave Method Menu Option	21
3.10	Alpha Channel Menu Option	22
3.11	Color Lookup Table Menu Option	23
3.12	Image Pixels Menu Option	24
3.13	Immediate Help Message Update	25
3.14	Output Message Text Window	25
3.15	Current Command String	26
3.16	Run Pushbutton	26
4	Conclusion	27
	References	29
	Glossary	31

List of Figures

FIGURE 1.	Several pop-up windows from the ximconv utility	2
FIGURE 2.	ximconv Main Window	6
FIGURE 3.	File Pulldown on the Menu Bar	10
FIGURE 4.	Input File Selection Dialog	11
FIGURE 5.	Output File Scrolled List Dialog	12
FIGURE 6.	Options Pulldown on the Menu Bar	13
FIGURE 7.	Help Pulldown on the Menu Bar	14
FIGURE 8.	On Version Cascade Menu	15
FIGURE 9.	ximconv Version Dialog	15
FIGURE 10.	imconv Version Dialog	16
FIGURE 11.	On imconv Arguments Cascade Menu	16
FIGURE 12.	Input Format Menu Option	18
FIGURE 13.	Output Format Menu Option	18
FIGURE 14.	Channel Depth Menu Option	19
FIGURE 15.	Channel/Pixel Menu Option	20
FIGURE 16.	Output Compression Menu Option	21
FIGURE 17.	Interleave Method Menu Option	22
FIGURE 18.	Alpha Channel Menu Option	23
FIGURE 19.	Color Lookup Table Menu Option	24
FIGURE 20.	Image Pixels Menu Option	25
FIGURE 21.	Immediate Help Message Update	25
FIGURE 22.	Output Message Text Window	26
FIGURE 23.	Current Command String	26
FIGURE 24.	Run Pushbutton	27

List of Tables

TABLE 1.	Ximconv File Formats	7
----------	--------------------------------	---

Ximconv User's Guide

Version 1.0.1

1 Introduction

The introduction section discusses a general overview of **ximconv**.

1.1 What is ximconv?

ximconv is a point and click utility for converting from one file format to another file format. Figure 1, on page 2, illustrates "Several pop-up windows from the **ximconv** utility".

More specially, **ximconv** is a MotifTM interface for the **imconv** file conversion utility developed by the San Diego Supercomputer Center (SDSC). The binaries for the SDSC Image Tools are available to Idaho National Engineering Laboratory¹ (INEL) employees through anonymous ftp on jade (134.20.8.49). A compressed tarfile of the binaries for the SPARCstation is named "pub/bin/sparc/ImageConvert/imtools.2.0.tar.z". A compressed tarfile of the binaries for the DECstation is also available on jade and is named "pub/bin/mips-ultrix-4.1/ImageConvert/imtools.2.0.tar.z". For installation details, consult your local system administrator.

1.2 Is ximconv available?

The source for **ximconv** is freely available to INEL employees.

1.3 What is needed to compile and execute?

To compile and link **ximconv**, you will need a c compiler (cc), the standard X11 release 4 libraries, and Motif version 1.1 or later.

To execute, **ximconv** requires that **imconv** and the other SDSC Image Tools be installed and on the user's current search path.

1. The Idaho National Engineering Laboratory facility is operated for the U.S. Department of Energy.

FIGURE 1. Several pop-up windows from the ximconv utility

1.3.1 How can I get a copy?

A compressed tar file of the source code is available through anonymous ftp on jade (134.20.8.49). The following work session outlines the procedure of getting a copy of that compressed tar file.

Make sure that your present working directory (pwd) is where you want the source located:

```
camas% mkdir src
camas% cd src
```

Transfer the file to your workstation:

```
camas% ftp jade
Connected to jade.
220 jade FTP server (SunOS 4.1) ready.
Name (jade:frm): anonymous
331 Guest login ok, send ident as password.
Password: frm@inatel.gov2
230 Guest login ok, access restrictions apply.
ftp> binary
200 Type set to I.
ftp> cd pub/src/utills
250 CWD command successful.
ftp> dir ximconv*
200 PORT command successful.
150 ASCII data connection for /bin/ls (134.20.24.3,1136) (0 bytes).
-rw-rw-rw- 1 ftp 1028079 May 7 16:45 ximconv-1.0.1.tar.Z
226 ASCII Transfer complete.
remote: ximconv*
66 bytes received in 0.19 seconds (0.34 Kbytes/s)
ftp> get ximconv-1.0.1.tar.Z
200 PORT command successful.
150 Binary data connection for ximconv-1.0.1.tar.Z (134.20.24.3,1137)
(1028079 bytes).
226 Binary Transfer complete.
local: ximconv-1.0.1.tar.Z remote: ximconv-1.0.1.tar.Z
1028079 bytes received in 4.9 seconds (2e+02 Kbytes/s)
ftp> quit
221 Goodbye.
camas% ls -lF *
-rw-rw-r-- 1 frm 1028079 May 13 11:38 ximconv-1.0.1.tar.Z
```

Uncompress and extract the source from the tar file:

```
camas% zcat ximconv-1.0.1.tar.Z | tar -xvf -
x ximconv-1.0.1/AlphaChannelCallback.c, 1514 bytes, 3 tape blocks
x ximconv-1.0.1/ChannelDepthCallback.c, 1458 bytes, 3 tape blocks
x ximconv-1.0.1/ChannelPixelCallback.c, 1457 bytes, 3 tape blocks
.
.
.
```

2. Your user id should be used here as the password. The password will *not* be echoed to the screen

```

camas% ls -lF
total 1018
drwxrwxr-x 5 frm 2048 May 7 10:40 ximconv-1.0.1/
-rw-rw-r-- 1 frm 1028079 May 13 11:38 ximconv-1.0.1.tar.Z
camas% cd ximconv-1.0.1
camas% ls -lF
total 1143
-rw-rw-r-- 1 frm 1514 Feb 21 13:08 AlphaChannelCallback.c
-rw-rw-r-- 1 frm 608 May 13 11:42 AlphaChannelCallback.o
-rw-rw-r-- 1 frm 1458 Feb 11 11:43 ChannelDepthCallback.c
.
.
.

```

1.3.2 How do I compile the source?

After extracting the source from the compressed tar file, you will need to generate the program by compiling the source. Several makefile templates are included for convenient compilation. For a SPARCstation, use "Makefile.sparc". For a DECstation, use "Makefile.dec". Copy the proper makefile to "Makefile".

```
camas% cp Makefile.sparc Makefile
```

The makefile should be edited to match your specific workstation environment. After editing the makefile, you are ready to compile.

```

camas% make ximconv
cc -I/usr/include/Xm -D_NO_PROTO -Dsparc -c AlphaChannelCallback.c
cc -I/usr/include/Xm -D_NO_PROTO -Dsparc -c ChannelDepthCallback.c
cc -I/usr/include/Xm -D_NO_PROTO -Dsparc -c ChannelPixelCallback.c
.
.
.
Linking ximconv ...
cc -I/usr/include/Xm -D_NO_PROTO -Dsparc AlphaChannelCallback.o
ChannelDepthCallback.o ChannelPixelCallback.o CloseManCallback.o ...
Pixmap.o -o ximconv -L/usr/export/lib/X11 -lXm -lXt -lX11 -lm
Compilation complete.

```

Upon successful compilation, the executable **ximconv** should be generated.

```

camas% ls -lF ximconv
-rwxrwxr-x 1 frm 262144 May 13 14:06 ximconv*

```

1.3.3 How do I install the program?

Again, the makefile should be edited to assure that the program will be installed in a location that everyone on your machine (or network) can access. You may also have to be super-user for this step. Contact your local system administrator for assistance.

```
camas% make install
```

```

Installing ximconv in /usr/local/bin ...
cp ximconv /usr/local/bin
cp ximconv.ad /usr/local/lib/X11/app-defaults/Ximconv
Installation complete.

```

After installing the binary, the object files are no longer needed:

```

camas% make clean
rm -f *.o core
Clean complete.

```

You may also wish to get rid of the local copy of the binary.

```

camas% make clobber
rm -f *.o core
Clean complete.
rm -f ximconv tags PACKING_LIST ./bin/ximconv*
rm -if ./doc/*.doc*
Clobber complete.

```

1.3.4 How do I execute ximconv?

At this point, if the installed program is on your search path, you should be able to execute **ximconv** by typing the command:

```
camas% ximconv &^3
```

The **ximconv** program should look similar to Figure 2, on page 6.

1.3.5 What if something goes wrong?

Again, contact your local system administrator if something goes awry on any of the steps previously mentioned. They are professionals and perform installation tasks routinely.

1.4 How does ximconv work?

The **ximconv** utility works pretty well when it does not core dump.

-
3. You may have to "rehash" before executing **ximconv** the first time, in order to add the new command to the hash table.
-

FIGURE 2. ximconv Main Window

1.5 How many file formats does it handle?

The `imconv` utility currently supports 28 different image file formats. Table 1, summarizes the supported file formats. The table also lists the recommended filename suffix or extension (the characters following the last period in the filename).

TABLE 1. `ximconv` file formats

Format Names		Description	Creator
Primary	Others		
eps	epi, epsf, epsi	Encapsulated PostScript file	Adobe
gif	giff	Compuserve Graphics Image File	Compuserve
hdf	df, ncsa	Hierarchical Data File	NCSA
icon	cursor, pr	Sun Icon and Cursor file	Sun Microsystems, Inc.
iff	suniff, taac	Sun TAAC Image File Format	Sun Microsystems, Inc.
mpnt	macp, pntg	Apple Macintosh MacPaint file	Apple Computer, Inc.
pbm		Portable Bit Map file	Jef Poskanzer
pcx	pcc	ZSoft IBM PC Paintbrush file	ZSoft Corp.
pgm		Portable Gray Map file	Jef Poskanzer
pic	picio, pixar	PIXAR picture file	PIXAR
pict	pict2	Apple Macintosh QuickDraw/ PICT file	Apple Computer, Inc.
pix	alias	Alias image file	Alias Research, Inc.
pnm		Portable aNy Map file	Jef Poskanzer
ppm		Portable Pixel Map file	Jef Poskanzer
ps	postscript	PostScript file	Adobe
ras	scr, sr, sun	Sun Rasterfile	Sun Microsystems, Inc.
rgb	iris, sgi	SGI RGB image file	Silicon Graphics, Inc.
rla	rlb	Wavefront raster image file	Wavefront
rle		Utah Run Length Encoded image file	Utah Raster Toolkit, University of Utah
rbpm		Raw Portable Bit Map file	Jef Poskanzer
rpgm		Raw Portable Gray Map file	Jef Poskanzer
rpnm		Raw Portable aNy Map file	Jef Poskanzer
rppm		Raw Portable Pixel Map file	Jef Poskanzer
synu		Synu image file	SDSC
tiff	tif	Tagged Image File	Aldus, MicroSoft, and NeXT
x	avs	Stardent AVS X image file	Stardent

TABLE 1. ximconv file formats

Format Names		Description	Creator
Primary	Others		
xbm	bm	X11 bitmap file	X Consortium
xwd	x11	X Window System window dump image file	X Consortium

2 Using ximconv

This section is a general discussion of how to use the **ximconv** utility.

2.1 Keyboard Shortcuts

Many of the popup dialogs and pulldown menus can be accessed by using keyboard *Accelerators* and *Mnemonics*. These are key-stroke shortcuts that you can use to quickly select an option without the use of a mouse.

2.1.1 KeyBoard Accelerators

Accelerators are keys that are assigned to a menu to execute that option directly. *Accelerators* are usually listed to the right of the label on menu pushbutton. You can use an *accelerator* even when the menu is not displayed. If an *accelerator* is available for a menu option, it will be indicated, in this documentation, within parenthesis “()” next to the section title.

2.1.2 KeyBoard Mnemonics

Mnemonics provide a similar capability to *accelerators* by allowing you to select a from menu by typing a single character. *Mnemonics* are listed as the underlined character in the label on menu pushbutton. You can use a *mnemonic* only when a menu is displayed. *Mnemonics* are indicated, in this documentation, as the character underlined in the section title.

2.2 Customizing ximconv

Many of the characteristics of **ximconv** can be modified by the user without re-compiling. This can be done through the command line upon execution, or by an entry in your application defaults file.

2.2.1 Command Line Options

The **ximconv** program handles many of the standard X11 command line switches. If you want to specify **ximconv** with a pink background and a navy foreground, the syntax would be as follows:

```
ximconv -background pink -foreground navy &
```

A list of permissible color names and their red, green, and blue values are found in the `"/usr/lib/X11/rgb.txt"` file. The color values and their associated color names can be displayed by using the program `"xcolors"` or `"xco"` by J. Korb, (jtk@cs.purdue.edu) and R. Bingle, (bingle@cs.purdue.edu). `"xco"` is available to INEL employees through anonymous ftp on jade as `"pub/src/X/xco.tar.z"`.

2.2.2 Application Defaults Options

An entry can also be placed in your local application defaults file (usually the `"~/.xdefaults"` file) to customize **ximconv**. The syntax for making **ximconv** come up with a dark slate blue background and a white foreground is as follows:

```
ximconv*background: DarkSlateBlue  
ximconv*foreground: white
```

The syntax for specifying the height and width of the mainWindowShell is as follows:

```
ximconv*mainWindowShell.height: 720  
ximconv*mainWindowShell.width: 750
```

Other **ximconv** application resources can be specified by copying the necessary system level resources from the file `"/usr/lib/X11/app-defaults/XImconv"` and adding them to the user's local application defaults file (`"~/.xdefaults"`).

After resources are added (or modified) in the `"~/.xdefaults"` file, the X server database must be updated in order for the changes to take place. This is done through the **xrdb** utility. If lines are added to the local application defaults file, you may wish to use **xrdb** with

the *merge* switch. This option merges only the new lines to the X server database. Note the syntax below:

```
xrdb -merge ~/.Xdefaults
```

If lines are deleted from the local application defaults file, you may wish to use **xrdb** with the *load* switch. This option replaces the entire contents of the database with the specified file. Note the syntax below:

```
xrdb -load ~/.Xdefaults
```

3 ximconv Main Window

The following is a discussion of the **ximconv** *Main Window*. The *Main Window* is the top level window displayed upon program execution. Figure 2, on page 6, illustrates the “ximconv Main Window”.

3.1 File Pulldown Menu (Meta+F)

The *File Pulldown Menu* (see Figure 3) from the menu bar on the main window has three options: *Input File*, *Output File*, and *Exit*.

FIGURE 3. File Pulldown on the Menu Bar

3.1.1 Input File... (Ctrl+I)

The *Input File Option* allows the user to specify the input file to convert. Upon selecting this option, the popup *Input File Selection Dialog* is displayed. Figure 4, on page 11, illustrates the “Input File Selection Dialog”.

The *File Selection Dialog* is used for traversing a directory structure and selecting an existing file.

The scrolling list on the left is a listing of sub-directories. Selecting a directory from the list will enable you to move “down” in the directory hierarchy. Also notice that directory “.” is available for moving “up” in a directory hierarchy.

The scrolling list on the right is a listing of files. The search for a particular file can be narrowed down by specifying a few unique alpha/numeric characters and a metacharacter (wildcard). To list all of the files with a “.xwd” extension for example, you would specify a “*.xwd” in the file filter text box located at the top of the dialog and select the *Filter Pushbutton*.

FIGURE 4. Input File Selection Dialog

After the user specifies the input file (using the *Select Pushbutton*), **ximconv** determines the file format and updates the *Input Format Menu Option* appropriately. See Section 3.4, on page 17, for a discussion of the “Input Format Menu Option”. If **ximconv** can not

determine the format of the specified file, the *Input Format Menu Option* will not be updated.

3.1.2 Output File... (Ctrl+O)

The *Output File Option* allows the user to specify the output filename of the new converted file. Upon selecting this option, the popup *Output File Scrolled List Dialog* (see Figure 5) is displayed.

The *Output File Scrolled List Dialog* is used for specifying a filename for the output file.

FIGURE 5. Output File Scrolled List Dialog

If the input file was specified previous to selecting this option, the prefix (defined as the string from the first character to the character before the last period) of the input filename is used when building the output filename selection list. This list offers the you reasonable alternatives for the output filename. You can also specify an output filename that is not on the list, by typing it in the text box on the dialog located above the pushbuttons. The *Output File Selection List* will continue to keep a history of previously entered and unique output filenames as long as a new input file is not specified.

After the you specify the output file, **ximconv** determines the desired output file format from the filename extension (see Table 1, on page 7) and updates the *Output Format Menu Option* appropriately. See Section 3.5, on page 18, for a discussion of the “Output Format Menu Option”. If the user specifies a filename with an extension that is not recognized by **ximconv** (i.e. filename.xyz) the *Output Menu Option* will not be updated.

3.1.3 Exit (Ctrl+X)

The *Exit Option* immediately terminates **ximconv**.

3.2 Options Pulldown Menu (Meta+O)

The *Options Pulldown Menu* (see Figure 6) from the menu bar on the main window has three options: *Feedback*, *Register*, and *Verbose*.

FIGURE 6. Options Pulldown on the Menu Bar

3.2.1 Feedback

The *Feedback Option* creates an **imconv** software feedback (bug report) form in the file “imconv.fbk.0”. This form can be sent to SDSC regarding the image convert utilities.

3.2.2 Register

The *Register Option* creates an **imconv** software user registration form in the file “imconv.reg.0”. This form can be sent to SDSC regarding the image convert utilities.

3.2.3 Verbose

The *Verbose Toggle* button controls whether or not **ximconv** displays output messages generated by **imconv** to the *Output Message Text Window* (see Figure 22, on page 26) during the course of the image file conversion. The **imconv** utility usually does its work silently. The *Verbose Toggle* is turned off by default.

3.3 Help Pulldown Menu (Meta+H)

The *Help Pulldown Menu* (see Figure 7) from the menu bar on the main window has three options: *On Version*, *On imconv Arguments*, *On Input File Type*, and *On Specific Formats*.

FIGURE 7. Help Pulldown on the Menu Bar

3.3.1 On Version...

The *On Version Cascade Button* (see Figure 8, on page 15) has two sub-menus: *ximconv*, and *imconv*. These buttons display the current version of the **ximconv** and **imconv** utilities.

FIGURE 8. On Version Cascade Menu

3.3.1.1 On Version *ximconv*

The *On Version ximconv Option* (see Figure 9) displays the popup *ximconv Version Dialog* notifying the user of the current version of the *ximconv* utility.

FIGURE 9. *ximconv* Version Dialog

3.3.1.2 On Version *imconv*

The *On Version imconv Option* displays the popup *ximconv Version Dialog* (see Figure 10, on page 16) notifying the user of the current version of the *imconv* utility.

FIGURE 10. imconv Version Dialog

3.3.2 On imconv Arguments...

The *On imconv Arguments Cascade Button* (see Figure 11) has two sub-menus: *Short Help*, and *Full Help*. These options display the arguments used by **imconv** to the *Output Message Text Window* (see Figure 22, on page 26).

FIGURE 11. On imconv Arguments Cascade Menu

3.3.2.1 On imconv Arguments Short Help

The *On imconv Arguments Short Help Option* displays a short help message to the *Output Message Text Window* (see Figure 22, on page 26) regarding the arguments to the **imconv** utility.

3.3.2.2 On imconv Arguments Full Help

The *On imconv Arguments Full Help Option* displays a full-length help message to the *Output Message Text Window* (see Figure 22, on page 26) regarding the arguments to the **imconv** utility.

3.3.3 On Input File Type

The *On Input File Type Option* uses the **imfile** utility to discern the image format of the input file previously specified (see Section 3.1.1, on page 10). The information is displayed to the *Output Message Text Window* (see Figure 22, on page 26).

imfile discerns the type of a file by first checking the file's magic number against a magic number list for known image formats. If the magic number doesn't match any of those in the list, **imfile** looks at the filename's suffix or extension (the characters following the last period in the filename) and checks the extension against a list of known image filename suffixes. See Table 1, on page 7, for "ximconv file formats".

If **imfile** can determine the format of a file, a message similar to the following is output:

```
thing2.hdf: 'hdf', Hierarchical Data File, NCSA
```

If **imfile** cannot determine the file format, a message similar to the following is output:

```
foo:          Unknown image file format
```

3.3.4 On Specific Formats...

The *On Specific Formats Option* has not been implemented.

3.4 Input Format Menu Option

The *Input Format Menu Option* (see Figure 12, on page 18) specifies the image format of the input file. Twenty-six file formats are currently being supported. See Table 1, on page 7, for a more verbose description of each file format. Encapsulated PostScript (EPS) and PostScript are not supported as input file formats by **imconv**. These two options are grayed out and not selectable.

FIGURE 12. Input Format Menu Option

3.5 Output Format Menu Option

The *Output Format Menu Option* (see Figure 13) specifies the image format of the output file. Twenty-eight file formats are currently being supported. See Table 1, on page 7, for a more verbose description of each file format.

FIGURE 13. Output Format Menu Option

3.6 Channel Depth Menu Option

The *Channel Depth Menu Option* (see Figure 14) specifies the output depth. The **imconv** man page states:

Some file formats allow color indexes and RGB values to be stored with a specific number of “bits-per-channel”. While 8 bits-per-channel is by far the most common, some formats support 1, 4, 12, 16, 24, and 32 bits-per-channel.

A color index image has 1 channel (the index into the color lookup table); an RGB image has 3 channels (red, green, and blue). The channel depth is the number of bits for each channel. So, an RGB image with an 8-bit channel depth takes $3 * 8 = 24$ bits per pixel. An RGB image with a 24-bit channel depth takes $3 * 24 = 72$ bits per pixel.

This option sets the number of bits to use per channel when writing out the image. If the output file format cannot support the number of bits per channel you specify, imconv reports an error and exits.

By default, imconv chooses the best number based on the number of bits per channel used by the incoming image. If an input file's image uses a 16-bit color index, imconv tries to output the image using a 16-bit, or more, color index. Truncation occurs only if the output format cannot support the incoming image's number of bits per channel, or anything larger. In fact, in the case of color index images, if imconv is given the choice of truncating a 16-bit color index image to 8 bits or converting it to RGB for the same output format, imconv converts it to RGB. imconv always chooses the path with the least degradation of the data.

FIGURE 14. Channel Depth Menu Option

3.7 Channel/Pixel Menu Option

The *Channel/pixel Menu Option* (see Figure 15) specifies the number of output channels. The **imconv** man page states:

The number of channels in an image is the number of values stored per pixel. A color index image has 1 channel (the color index into the color lookup table). An RGB image has 3 channels (red, green, and blue). Though channel numbers other than 1 or 3 are possible, in practice they aren't used. (We don't count the alpha channel.)

This option selects the number of channels per pixel (not including the alpha channel) to use when writing the image.

This option is provided as a path towards future functionality. In the present release, this option provides the same information as the Image Pixels options.

FIGURE 15. Channel/Pixel Menu Option

3.8 Output Compression Menu Option

The *Output Compression Menu Option* (see Figure 16, on page 21) specifies the compression format of the output file. The **imconv** man page states:

Most image file formats support compression schemes to reduce the size of a file. Some formats even support multiple compression schemes.

This option is the name of the compression scheme to use:

none	uncompressed
lzw	Lempel-Ziv & Welsh compressed
pb, packbits, mac	Apple Macintosh Packbits
rle	Run-Length-Encoded

Uncompressed images store each image pixel as a value or values in the file. No tricks are applied to reduce the disk space requirements. Uncompressed image files take longer to write out and read in, and they use up more disk space (often several times as much as a well compressed image).

Compression schemes use trickery to reduce the storage requirements of the image. The most common among these is Run-Length Encoding (RLE). RLE is based on the fact that most images have runs of adjacent pixels of the same color, such as solid color image backgrounds. These runs can be abbreviated to just a count of the number of pixels in the run, and the color to use for the run. Run-length-encoded images usually take 30-50% less disk space.

Most image formats support some variant of RLE compression. Since these variants are similar, imconv refers to them all as "rle compression."

Lempel-Ziv & Welsh and Apple's Packbits compression are fancier and too complex to explain here.

If the output format does not support the form of compression you select with this option, imconv reports an error and exits.

By default, imconv chooses the most efficient or most widely used compression scheme supported by the output file format.

FIGURE 16. Output Compression Menu Option

3.9 Interleave Method Menu Option

The *Interleave Method Menu Option* (see Figure 17, on page 22) specifies the interleaving method of the output file. The **imconv** man page states:

This option only applies to RGB images.

RGB images are written out using one of the following three methods:

non-interleaved	RGBRGBRGBRGB...
scanline-interleaved	RR..GG..BB..RR..GG..BB...
plane-interleaved	RRRR..GGGG..BBB..

Some formats support all three methods. Other formats support only one or two. This option takes one of the following arguments:

none	non-interleaved
line	scanline-interleaved

plane plane-interleaved

If the output format does not support the interleave method you select, imconv reports an error and exits.

By default, imconv chooses the most efficient or most widely used interleave method for the output format. In most cases imconv chooses plane-interleaved over scanline-interleaved, and scanline-interleaved over non-interleaved. This is because image compression schemes (see below) work better on plane- and scanline-interleaved images, thus reducing the amount of disk space an image file requires.

FIGURE 17. Interleave Method Menu Option

3.10 Alpha Channel Menu Option

The *Alpha Channel Menu Option* (see Figure 18, on page 23) specifies the output alpha channel. The **imconv** man page states:

An alpha channel contains a coverage value for each image pixel and typically is used when compositing images. For instance, to make image ABC partially cover XYZ, parts of ABC are marked as opaque (they cover XYZ), while other parts are transparent (XYZ shows through).

Alpha values typically range from 0 to 255. 0 means transparent, 255 opaque. Values between 0 and 255 indicate partial transparency and direct compositing software to mix the color of the image on top with the color of the image below, using the alpha value as a weighting factor.

The *Alpha Option* directs that an alpha channel be output for the image. If the *Alpha Option* is given and the output format cannot support an alpha channel (most cannot), imconv reports an error and exits.

The *No Alpha Option* directs that an alpha channel not be output. If the *No Alpha Option* is given and the output format must have an alpha channel (rare), imconv reports an error and exits.

If the incoming image does not have an alpha channel but you specify the *Alpha Option*, imconv automatically generates an opaque alpha channel (all 255s).

By default, if the incoming image has an alpha channel, imconv tries to write it out. For some file formats, only RGB images, not color index images, can be stored with alpha channels. In such

cases, if the incoming image is a color index image with an alpha channel, imconv automatically converts the image to RGB to preserve the alpha channel.

FIGURE 18. Alpha Channel Menu Option

3.11 Color Lookup Table Menu Option

The *Color Lookup Table Menu Option* (see Figure 19, on page 24) specifies the output of a color lookup table (CLT). The **imconv** man page states:

Color index images usually have a CLT associated with them. RGB images can also have them, though less commonly.

Some image file formats allow the CLT to be left out of the image file. The *No CLT Option* directs imconv to not write the CLT. The *CLT Option*, directs imconv to write the CLT.

Some formats require the CLT to be included in the file. In such cases, if you specify the *No CLT Option*, imconv reports an error and exits, since it is unable to comply with your request.

In much rarer cases, some formats do not allow a CLT to be stored in the image file. If you specify the *CLT Option*, imconv reports an error and exits.

If the incoming image does not have a CLT but you specify the *CLT Option*, imconv writes a ramping CLT (low to high). This is most common when reading in a grayscale image (color index image without a CLT) and writing out a color image (color index image with a gray ramp for a CLT).

By default, if the incoming image has a CLT, imconv attempts to store it. If the output format cannot store a CLT but can store an RGB image, imconv automatically converts a color index image to an RGB image and stores it that way.

FIGURE 19. Color Lookup Table Menu Option

3.12 Image Pixels Menu Option

The *Image Pixels Menu Option* (see Figure 20, on page 25) specifies the output to color index or RGB image. The `imconv` man page states:

Typically, image pixels are represented as color index (pseudo-color) or RGB (true-color) values.

A color index is a small integer (usually 8- or 12-bits) that indexes into an associated color lookup table (CLT) to get the red-green-blue (RGB) color value for a pixel in the image. A color index image is often referred to as a “pseudo-color” image because the color for a given pixel is found in the CLT, not in the pixel data itself.

An RGB image stores the red-green-blue (RGB) value for a pixel's color for every pixel in the image. There is no associated CLT. RGB images are often referred to as “true-color” because the full color description (RGB value) is stored in each pixel.

The *Color Index Option* forces `imconv` to convert the incoming image to a color index image before writing it to the output file. If the output file format cannot support storing a color index image, then `imconv` reports an error and exits.

The *Color Index Option* forces `imconv` to convert the incoming image to an RGB image before writing it to the output file. If the output file format cannot support storing an RGB image, then `imconv` reports an error and exits.

By default, if the input file's image is a color index image, `imconv` tries to write it out as a color index image. Similarly, if the input file's image is an RGB image, `imconv` tries to write it out as an RGB image. If the output format doesn't support what `imconv` wants, `imconv` automatically converts the image to one of the supported output file format variants.

FIGURE 20. Image Pixels Menu Option

3.13 Immediate Help Message Update

The *Immediate Help Message Update* is a drawn button that provides contextual, informative, feedback messages for most all of the pushbuttons. Figure 21, on page 25, illustrates the "Immediate Help Message Update". The message should provide information regarding one of the following:

1. The operation that will take place when the pushbutton is clicked (when mouse button one is pressed and released).
2. An elaboration of the option that the pushbutton or toggle represents.

FIGURE 21. Immediate Help Message Update

The help message is updated when a pushbutton is armed (when mouse button one is depressed).

3.14 Output Message Text Window

The *Output Message Text Window* (see Figure 22, on page 26) is a read-only scrolling text window that *ximconv* uses to display output information.

FIGURE 22. Output Message Text Window

3.15 Current Command String

The *Current Command String* (see Figure 23) is a scrolling text box that specifies the current command string built by *ximconv*. This is the command string that will be executed when the *Run Pushbutton* (see Section 3.16) is clicked or when a carriage return is made while focus is in this text box. Additional switches to *imconv* or other system commands may be input directly in this text box.

FIGURE 23. Current Command String

3.16 Run Pushbutton

The *Run Pushbutton* (see Figure 24, on page 27) executes the text in the *Current Command String* scrolling window.

FIGURE 24. Run Pushbutton

4 Conclusion

I hope you enjoy **ximconv** and find it useful. I have had fun coding it. Your *polite* comments and bug fixes are welcome. I always enjoy learning new things, especially the right way to do something.

Fred R. McClurg
frm@inel.gov

References

- Boge P. and Cullen C., 1992, *Atlas, A File Conversion Matrix*, EGG-CODP-10020, January 1992
- Frame Technology Corporation, 1990, *FrameMaker Reference*, San Jose, California
- Frame Technology Corporation, 1990, *Using FrameMaker*, San Jose, California
- Heller, D., 1991, *Motif Programming Manual, Volume Six*, Sebastopol, California: O'Reilly & Associates, Inc., Publisher
- Johnson, E. and Reichard, K., 1991, *Power Programming... MOTIF*, Portland, Oregon: Management Information Source, Inc., Publisher
- Massachusetts Institute Technology X Consortium, 1992, "X Window System, Version 11", Cambridge, Massachusetts
- Nadeau, D., 1991, "imconv, imfile", *UNIX Man Pages*, San Diego Supercomputer Center, consult@y1.sdsc.edu
- Open Software Foundation, Inc., 1990, *OSF/Motif™ User's Guide, Revision 1.0*, Englewood Cliffs, New Jersey: Prentice Hall Publishing Company, Inc.
- Quercia, V. and O'Reilly, T., 1990, *X Window System User's Guide, Volume Three*, Sebastopol, California: O'Reilly & Associates, Inc., Publisher
- Sobell, M., 1989, *A Practical Guide to the UNIX System*, 2nd ed., Redwood City, California: Benjamin/Cummings Publishing Company, Inc.
- Talbott, S., 1988, *Managing Projects with Make*, Newton, Massachusetts: O'Reilly & Associates, Inc., Publisher

Glossary

cat: Unix command to concatenate or display files.

cc: Unix command to access the c compiler.

cd: Unix command to change working directory.

cp: Unix command to copy a file.

FrameMaker: A commercial, What-You-See-Is-What-You-Get (WYSIWYG) desktop publishing package by Frame Technology Corp., San Jose, CA. FrameMaker generates publication-quality documentation through a motif-like, point-and-click user interface. FrameMaker version 3.1x was used to generate this documentation.

ftp: Acronym that stands for File Transfer Protocol. FTP is used to transfer files from one machine on the network to another.

imconv: A public domain utility developed by D. Nadeau of the San Diego Supercomputer Center (SDSC) for converting between image file formats.

imfile: Unix utility developed by D. Nadeau of the San Diego Supercomputer Center (SDSC) for discerning the image format of a file(s).

INEL: Acronym that stands for Idaho National Engineering Laboratory, located in Idaho Falls. The INEL facility is operated for the U.S. Department of Energy.

lpr: Unix command to queue file(s) to a network printer.

ls: Unix command to display information about one or more files.

make: Unix utility to update files. The make utility is most often used to compile and link a set of program source files.

makefile: An ASCII database, used by the make utility, that contains Unix commands and defines file relationships.

mkdir: Unix command to make a directory.

Motif: Programmer's toolkit library designed by the Open Software Foundation (OSF), based on the X Toolkit (Xt) Intrinsics. Motif is used for creating user interfaces with buttons that have a 3D look and feel.

pwd: Unix command to display pathname of the current working directory.

rgb.txt: The ASCII database that assigns names to red, green, blue, values. Those names can then be used by many X-based programs.

rm: Unix command to remove a file(s).

SDSC: Acronym that stands for San Diego Supercomputer Center.

tar: Unix command for storing or retrieving files from an archive file or tape.

xco: An interactive, public domain program by J. Korb and R. Bingle for displaying X11 colors and their associated color names. xco can also be used for comparing combinations of background and foreground colors.

xcolors: A program for displaying X11 colors and their associated color names.

.Xdefaults: The ASCII database that allows a user to customize an X application without recompiling.

ximconv: A point and click motif user interface to the Image Tools developed by the San Diego Supercomputer Center (SDSC). ximconv was written by F. McClurg.

xrdb: A utility used for updating the X server resource database.

zcat: Unix command that reads a compressed file and generates uncompressed output while leaving the original file intact. zcat eliminates the need to uncompress (and later compress) a file while extracting files from a compressed tarfile, for example.

END

**DATE
FILMED**

8 / 25 / 92