EGG--CODP--10230

DE92 018045

Vectum User's Guide

Fred R. McClurg
Vincent A. Mousseau

April 1992

Idaho National Engineering Laboratory
EG&G Idaho, Inc.
Idaho Falls, Idaho 83415

Prepared for the
U.S. Department of Energy
Field Office, Idaho
Under DOE Contract No. DE-AC07-76ID01570

MASTER

DISTRIBUTION OF THIS DOCUMENT IS UNLIMITED

Abstract

This user's guide is the documentation for **vectum**: the easy to use, flexible, multi-purpose, 2D velocity vector plotting package based on the NCAR Graphics libraries.

Acknowledgments

The authors would like to express their appreciation to the following:

Technical Services, Visualization and Imaging Team
Computational Fluid Dynamics Unit
Partial Support from the Long-term Research Initiative in Computational Mechanics

2.1.21	Theta parameter	17
2.1.22	Scarro parameter	18
2.1.23	Shfmin parameter	18
2.1.24	Altchr parameter	18
2.1.25	Arwehr parameter	22
2.1.26	Arwsiz parameter	24
2.1.27	Arwang parameter	24
2.1.28	Useshf parameter	25
2.1.29	Decinc parameter	26
2.1.30	Vecmin parameter	29
2.1.31	Optmin parameter	29
2.1.32	Vecmax parameter	30
2.1.33	Optmax parameter	30
2.1.34	Movie parameter	33
2.2	Geometry database	33
2.2.1	Comment descriptor	36
2.2.2	Dash descriptor	36
2.2.3	Line descriptor	37
2.2.4	String descriptor	38
2.2.5	Arc (circle) descriptor	40
2.2.6	Curve (spline) descriptor	41
2.3	Vector database	42
3	Vectum Output	43
3.1	Displaying to a monitor	43
3.1.1	X11 driver	43
3.1.2	Tektronix driver	44
3.2	Submission to a printer	44
3.2.1	PostScript driver	44
3.2.2	Impress driver	44
3.2.3	HPLJ driver	45
3.3	Generating a file	45
3.3.1	PostScript file	45
3.3.2	XWD file	45
3.3.3	Sun Raster file	46
3.3.4	Encapsulated PostScript file	46
	References	49
	Glossary	51

Table of Contents

Abstract	iii
Acknowledgments	iv
Table of Contents	v
List of Figures	vii
Vectum User's Guide	1
1 Introduction	1
1.1 What is vectum?	1
1.1.1 What are the distinguishing features?	1
1.1.2 How does it work?	1
1.2 Is vectum available?	1
1.2.1 What is needed to compile and execute?	2
1.2.2 How can I get a copy?	2
1.2.3 How do I compile the source?	3
2 Using Vectum	4
2.1 Parameter file	4
2.1.1 Parameter file syntax	4
2.1.2 Value field	5
2.1.3 Comment field	5
2.1.4 Title parameter	5
2.1.5 Titsiz parameter	6
2.1.6 Filein parameter	6
2.1.7 Filout parameter	6
2.1.8 Filgeo parameter	6
2.1.9 Filpal parameter	6
2.1.10 Xmin parameter	7
2.1.11 Xmax parameter	7
2.1.12 Ymin parameter	7
2.1.13 Ymax parameter	8
2.1.14 Sf parameter	9
2.1.15 Multsf parameter	9
2.1.16 Loguni parameter	12
2.1.17 Frac parameter	14
2.1.18 Flex parameter	15
2.1.19 Useaxs parameter	16
2.1.20 Useleg parameter	17

List of Figures

FIGURE 1.	Components of a viewport window	8
FIGURE 2.	Scale factor of 0.5	10
FIGURE 3.	Scale factor of 2.0	11
FIGURE 4.	Unit vector shaft scaling	12
FIGURE 5.	Normal vector shaft scaling	13
FIGURE 6.	Logarithmic vector shaft scaling	14
FIGURE 7.	Equal unit scaling in the x and y directions	15
FIGURE 8.	Independent x and y scaling	16
FIGURE 9.	Line arrowhead parameters	17
FIGURE 10.	Alternate character set	19
FIGURE 11.	Alternate character set (cont.)	20
FIGURE 12.	Alternate character set (cont.)	21
FIGURE 13.	Alternate character set (cont.)	22
FIGURE 14.	Characters in the same function code family	23
FIGURE 15.	Characters in differing function code families	24
FIGURE 16.	Scatter plot with a constant marker size	25
FIGURE 17.	Scatter plot with a variable marker size	26
FIGURE 18.	Line arrowheads with decimation factor of 1	27
FIGURE 19.	Line arrowheads with decimation factor of 5	28
FIGURE 20.	Specifying a range using a logical operator	29
FIGURE 21.	Finite range specified	31
FIGURE 22.	Minimum range specified	32
FIGURE 23.	Maximum range specified	32
FIGURE 24.	Infinite range specified	33
FIGURE 25.	Miscellaneous geometry defined by the geometry database	35
FIGURE 26.	Geometry drawn using the dash descriptor	37

FIGURE 27. Triangular grid mesh drawn using the line descriptor	38
FIGURE 28. Geometry drawn using the string descriptor	39
FIGURE 29. Geometry drawn using the arc (circle) descriptor	40
FIGURE 30. Geometry drawn using the curve (spline) descriptor	41
FIGURE 31. Coordinates of a velocity vector	42
FIGURE 32. Imported Sun Raster file	46
FIGURE 33. Imported Encapsulated PostScript file	47

Vectum User's Guide

1 Introduction

This document is intended to serve as a general reference for **vectum**, the vector utility.

1.1 What is vectum?

Vectum is an easy to use, flexible, multi-purpose, 2D velocity vector, plotting package. It is also capable of generating particle plots (scatter plots), xy plots, and geometries.

1.1.1 What are the distinguishing features?

The program **vectum** allows the user to display irregular vector fields quickly and easily. It also gives the user the flexibility of modifying the characteristics of the vectors without re-compilation.

Vectum uses the NCAR Graphics Libraries to generate publication quality output of a 2D vector field. All of the NCAR Graphics utilities can be used with the output from **vectum**.

1.1.2 How does it work?

Vectum uses a parameter file to set the program's behavior. This file controls the scaling of the vectors, annotation, dataset filename, and several other details. After determining the filename specified in the parameter file, **vectum** reads the ASCII database of irregular vector values and generates a NCAR CGM (Computer Graphics Metafile) file that can be displayed and plotted using the NCAR Graphics utilities.

1.2 Is vectum available?

The source for **vectum** is freely available to Idaho National Engineering Laboratory (INEL) employees.

1.2.1 What is needed to compile and execute?

A FORTRAN 77 (f77) compiler and the NCAR Graphics Libraries and utilities.

1.2.2 How can I get a copy?

A compressed tar file of the source code is available through anonymous ftp on jade (134.20.8.49). The following work session outlines the process of getting a copy of that compressed tar file.

Make sure that your present working directory (pwd) is where you want the source located:

```
camas% mkdir src
camas% cd src
```

Transfer the file to your workstation:

```
camas% ftp jade
Connected to jade.
220 jade FTP server (SunOS 4.1) ready.
Name (jade:frm): anonymous
331 Guest login ok, send ident as password.
Password: frm@inel.gov
230 Guest login ok, access restrictions apply.
ftp> binary
200 Type set to I.
ftp> cd pub/src/graphics
250 CWD command successful.
ftp> get vectum-1.0.tar.Z
200 PORT command successful.
150 Binary data connection for vectum-1.0.tar.Z (134.20.8.49.1165) (41340
bytes).
226 Binary Transfer complete.
local: vectum-1.0.tar.Z remote: vectum-1.0.tar.Z
41340 bytes received in 0.94 seconds (1e+03 Kbytes/s)
ftp> quit
221 Goodbye.
camas% ls -lF
total +1
-rw-rw-r-- 1 frm 41340 Apr 1 12:45 vectum-1.0.tar.Z
```

Uncompress and extract the source from the tar file:

```
camas% zcat vectum-1.0.tar.Z | tar -xvf -
x vectum-1.0/arcsiz.f, 3625 bytes, 8 tape blocks
x vectum-1.0/arwlin.f, 2869 bytes, 6 tape blocks
x vectum-1.0/autosf.f, 2436 bytes, 5 tape blocks
.
.
.
camas% ls -lF
total 42
```

```

drwxrwxr-x 2 frm 1024 Apr 1 12:34 vectum-1.0/
-rw-rw-r-- 1 frm 41340 Apr 1 12:45 vectum-1.0.tar.Z
camas% cd vectum-1.0
camas% ls -lF
total 137
-rw-rw-r-- 1 frm 3625 Jul 17 1991 arcsiz.f
-rw-rw-r-- 1 frm 2869 Jul 17 1991 arwlin.f
-rw-rw-r-- 1 frm 2436 Jul 17 1991 autosf.f
.
.
.

```

1.2.3 How do I compile the source?

After extracting the source from the compressed tar file, you will need to generate the program by compiling the source. A makefile is included for convenient compilation.

```

camas% make
f77 -sun4 -c vectum.f
vectum.o:
MAIN vectum:
f77 -sun4 -c arcsiz.f
arcsiz.o:
arcsiz:
f77 -sun4 -c arwlin.f
arwlin.o:
arwlin:
.
.
.
nearcf77 -o vectum vectum.o arcsiz.o arwlin.o autosf.o ... -lm -smooth
Smooth f77 of NCAR Graphics
f77 -o -Bstatic -o vectum vectum.o ... -lm /usr/local/lib/libdashsmth.o
/usr/local/lib/libncard.a /usr/local/lib/libncard_qks.a
/usr/local/lib/libncard_loc.a

```

Upon successful compilation, the executable **vectum** should be generated.

```

camas% ls -lF vectum
-rwxrwxr-x 1 frm 573440 Apr 1 12:53 vectum*

```

After generating the binary, the object files are no longer needed:

```
camas% rm *.o
```

At this point you may wish to contact your system administrator to have the program installed in a location that everyone on your machine (or network) can access.

2 Using Vectum

The following is a description for using the velocity vector package, **vectum**.

2.1 Parameter file

Upon execution, **vectum** reads an ASCII parameter file named "default.vec" in the user's present working directory (pwd). The parameter file contains information that the user can modify to control how the program is executed and how the resulting vector field is displayed. The following is a listing of an example parameter file:

```
damas% cat default.vec
"Log Vector Field 'KRL'-'*/-'KGU-'Z'PGL'AB" # title plot title
0.017 # ttsiz title size
'vector.dat' # filein input filename.
'meta' # filout output filename [not implimented]
'geom.geo' # filgeo geometry definition file. Specify '' if not used.
'palette.pal' # filpal palette file. Specify '' if not used. [not imp.]
0.0 # xmin if (xmax <= xmin) automatic max/min window
0.0 # xmax if (xmax <= xmin) automatic max/min window
0.0 # ymin if (ymax <= ymin) automatic max/min window
0.0 # ymax if (ymax <= ymin) automatic max/min window
0.0 # st if (st <= 0.0) automatic scale factor
1.0 # multsf scale factor multiplier
0 # loguni (-1) unit scale (0) normal scale (1) log scale
1 # trac (0) max/min win next int (1) max/min win near float
0 # flex (0) equal spacing in x/y (1) max/min x/y to fill window
1 # useaxs (0) axis not displayed (1) display axis
1 # useleg (0) legend not displayed (1) display legend
30.0 # theta degree angle between vector shaft & hypot arrow leg
15 # scarro arrow length (triangle height) is % of vector shaft
0.2 # shmin minimum arrow size
0 # alchr (-1) line arrowhead (0) normal charset (1) extend charset
'x' # arwchr arrowhead character
20 # arwsiz maximum arrowhead size
0 # arwang arrowhead angle
1 # useshf (-1) scatter [constant head] (0) no shaft (1) use shaft
1 # decinc decimation increment. decinc = 1 for every value
0.0 # vecmin minimum vector length
'?' # optmin display values ( <, >, <=, >=, ==, ? ) vecmin length
0.0 # vecmax maximum vector length
'?' # optmax display values ( <, >, <=, >=, ==, ? ) vecmax length
1 # movie (0) merge multiple frame (1) append multiple frame
```

2.1.1 Parameter file syntax

Each line in the parameter file controls a different aspect of the program. Each line is necessary and the order of the lines must not be changed. The syntax of the parameter file is as

follows:

```
value    # variable    (0) option one    (1) option two    ...
```

As far as the program is concerned, there are really only two fields to each line. The *value* field and the *comment* field. The fields are delimited by spaces or tabs.

2.1.2 Value field

The *value* is the first field on the line and can contain an integer, floating point, or character type variable depending upon the context. The *value* field must transcribe to the following rules:

- Fields using an integer context, should not contain points or characters.
- Fields using a floating point context, should contain one point and no characters (except the exponential information).
- Fields using a character string context, should begin in column one and be surrounded with single quotes (') or double quotes (").

2.1.3 Comment field

The *comment* is the second field on the line and begins with the symbol #. Everything following the symbol # is ignored by **vectum**. The *comment* field contains several pieces of information that is descriptive of the *value* field.

The *variable tag* is the first word in the *comment* field. It is used as a cryptic handle to describe the purpose of the *value* field. In this documentation, each parameter will be listed according to it's *variable tag*.

The *option tag* follows the *variable tag* in the *comment* field. It is used to inform individuals regarding the setting of the *value* field.

2.1.4 Title parameter

The *title* parameter is the string that is centered at the top of the plot. The *title* parameter is of type character string. Note the following example:

```
"Vector Field 'KRL'-'*/','KGU'Z'PGL'AB" # title plot title
```

The *title* string must be enclosed with single quotes (') or double quotes ("). Any character can be used within the string except a single quote, double quote or grave (`) symbol. The grave symbol is reserved to display special characters. See Section 2.1.25, on page 22 for

a description of the *Alternate Character Set*.

2.1.5 Titsiz parameter

The *titsiz* parameter controls the size of *title* string centered at the top of the plot. The *titsiz* parameter is of type float. Note the following example:

```
0.017 # titsiz title size
```

2.1.6 Filein parameter

The *filein* parameter is the filename of the vector database. See Section 2.3, on page 42 for the file format of the vector database. The *filein* parameter is of type character string. Note the following example:

```
'vector.dat' # filein input filename.
```

2.1.7 Filout parameter

The *filout* parameter is the filename of the CGM file output by **vectum**. The *filout* parameter is of type character string. Note the following example:

```
'gmeta' # filout output filename [not implemented]
```

This parameter is not currently implemented programatically within **vectum**. The default output CGM filename "gmeta" can be changed to a user specified name by setting the following environment variable:

```
host$ setenv NCARG_GKS_OUTPUT myfile.cgm
```

2.1.8 Filgeo parameter

The *filgeo* parameter is the name of the geometry database. See Section 2.2, on page 33 for the file format of the geometry database. The *filgeo* parameter is of type character string. Note the following example:

```
'geom.geo' # filgeo geom file Specify '' if not used.
```

2.1.9 Filpal parameter

The *filpal* parameter is the name of the palette database. The *filpal* parameter is of type character string. Note the following example:

'palette.pal' # filpal palette Specify '' if not used.

This parameter is not currently implemented.

2.1.10 Xmin parameter

The *xmin* parameter is the minimum value of the viewport window in the x direction. The *xmin* parameter is of type float. See Figure 1, on page 8 for an illustration of *xmin* on a viewport window. Note the following example:

```
0.0      # xmin      if (xmax <= xmin) auto max/min window
```

If the value of the *xmax* parameter is less than or equal to the *xmin* parameter, **vectum** will automatically maximize/minimize the viewport so that the entire data field will fill the window.

2.1.11 Xmax parameter

The *xmax* parameter is the maximum value of the viewport window in the x direction. The *xmax* parameter is of type float. See Figure 1, on page 8 for an illustration of *xmax* on a viewport window. Note the following example:

```
0.0      # xmax      if (xmax <= xmin) auto max/min window
```

If the value of the *xmax* parameter is less than or equal to the *xmin* parameter, **vectum** will automatically maximize/minimize the viewport so that the entire data field will fill the window.

2.1.12 Ymin parameter

The *ymin* parameter is the minimum value of the viewport window in the y direction. The *ymin* parameter is of type float. See Figure 1, on page 8 for an illustration of *ymin* on a viewport window. Note the following example:

```
0.0      # ymin      if (ymax <= ymin) auto max/min window
```

If the value of the *ymax* parameter is less than or equal to the *ymin* parameter, **vectum** will automatically maximize/minimize the viewport so that the entire data field will fill the window.

2.1.13 Ymax parameter

The *y*max parameter is the maximum value of the viewport window in the y direction. The *y*max parameter is of type float. See Figure 1, on page 8 for an illustration of *y*max on a viewport window. Note the following example:

```
0.0    # ymax    if (ymax <= ymin) auto max/min window
```

If the value of the *y*max parameter is less than or equal to the *y*min parameter, **vectum** will automatically maximize/minimize the viewport so that the entire data field will fill the window.

FIGURE 1. Components of a viewport window

2.1.14 Sf parameter

The *sf* parameter is the scale factor **vectum** uses internally to make the vectors a reasonable size. The *sf* parameter is of type float. Note the following example:

```
0.0      # sf      if (sf <= 0.0) automatic scale factor
```

If the value of the *sf* parameter is less than or equal to zero, **vectum** will automatically determine the scale factor and report the calculated value to the standard output. You may want to use this parameter to maintain a common scale factor between two plots that are to be merged together. You may also want to use this parameter to eliminate the automatic vector shaft scaling in order to compare two different datasets. Figures 18 and 19 on pages 27 and 28 were generated by setting the *sf* parameter on the second plot (Figure 19) to the value that was calculated and reported to standard out by the first plot (Figure 18).

2.1.15 Multsf parameter

The *multsf* parameter is the scale factor multiplier. This parameter enables the user to easily scale the size of the vectors. The *multsf* parameter is of type float. Note the following example:

```
1.0      # multsf      scale factor multiplier
```


If the value of the *multsf* parameter is less than one, **vectum** will reduce the length of the vector shaft. See Figure 2.

FIGURE 2. Scale factor of 0.5

If the value of the *multsf* parameter is greater than one, **vectum** will enlarge the length of the vector shaft. See Figure 3.

FIGURE 3. Scale factor of 2.0

The *multsf* parameter should never be zero (0.0) or less than zero.

2.1.16 Loguni parameter

The *loguni* parameter is a three way switch for displaying unit vectors, normal scaled vectors, and log scaled vectors. The *loguni* parameter is of type integer. Note the following example:

```
0 # loguni (-1) unit vector (0) normal (1) log
```

If the value of the *loguni* parameter is negative one (-1), **vectum** will set the vector shaft scaling to unit scaling (see Figure 4). Unit scaled vectors have a constant vector length and indicate only the vector direction (and not the intensity). Zero length vectors will not be displayed due to the age old question, "What direction do zero length vectors go?"

FIGURE 4. Unit vector shaft scaling

If the value of the *loguni* parameter is zero (0), **vectum** will set the vector shaft scaling in proportion to the u/v values. See Figure 5.

FIGURE 5. Normal vector shaft scaling

If the value of the *loguni* parameter is one (1), **vectum** will set the vector shaft scaling to logarithmic scaling (see Figure 6). Logarithmic scaled vectors have a logarithm ($\log(x)$) applied to each vector length.

FIGURE 6. Logarithmic vector shaft scaling

2.1.17 Frac parameter

The *frac* parameter is the float/integer toggle that determines the type of rounding that is used when the window viewport is automatically maximized/minimized. The *frac* parameter is of type integer. Note the following example:

```
1 # frac      (0) max/min win int    (1) max/min win float
```

If the value of the *frac* parameter is zero (0) and the *xmin/xmax* or *ymin/ymax* parameter is set to automatically maximize/minimize the window, the viewport will be zoomed to the next largest integer that is outside of the vector field.

If the value of the *frac* parameter is one (1) and the *xmin/xmax* or *ymin/ymax* parameter is set to automatically maximize/minimize the window, the viewport will be zoomed to the nearest floating point value that is outside of the vector field.

2.1.18 Flex parameter

The *flex* parameter is the toggle that controls whether the x and y axis is scaled with respect to each other or independently of one another. The *flex* parameter is of type integer. Note the following example:

```
0 # flex (0) equal space x/y (1) max/min x/y & fill win
```

If the value of the *flex* parameter is zero (0), the viewport will be scaled so that the units in the x direction will be equal in length to the units in the y direction. See Figure 7.

FIGURE 7. Equal unit scaling in the x and y directions

If the value of the *flex* parameter is one (1), the viewport will be scaled so that the units in the x and y direction will depend upon the outer extent of the vector field. If the vector field extends farther in the x direction than the y direction, for example, the units in the x direction will be closer together than the y direction. The axis scale "flexes" to accommodate the maximum unit value in x and y direction. Changing the axis independently forces vector data to fill the entire viewport window. See Figure 8.

FIGURE 8. Independent x and y scaling

Scaling the x and y axis with respect to the data field and independently of each other may *not* be appropriate for unit scaled vectors.

2.1.19 Useaxis parameter

The *useaxis* parameter is the toggle that turns the display of the axis off and on. The axis includes the tickmarks, and the axis values. The *useaxis* parameter is of type integer. See Figure 1, on page 8 for an illustration of the axis on a viewport window. Note the following

example:

```
1 # useaxis (0) axis not displayed (1) display axis
```

If the value of the *useaxis* parameter is zero (0), the axis will not be displayed. If the value of the *useaxis* parameter is one (1), the axis will be displayed.

2.1.20 Useleg parameter

The *useleg* parameter is the toggle that turns the display of the legend off and on. See Figure 1, on page 8 for an illustration of the legend on a viewport window. The value of the *useleg* parameter is of type integer. Note the following example:

```
1 # useleg (0) legend not display (1) display legend
```

If the value of the *useleg* parameter is zero (0), the legend will not be displayed. If the value of the *useleg* parameter is one (1), the legend will be displayed.

2.1.21 Theta parameter

The *theta* parameter is the angle (in degrees) between the vector shaft and the hypotenuse of arrow leg on line arrowheads. See Figure 9 for an illustration of the line arrowhead parameters. The *theta* parameter is of type float. Note the following example:

```
30.0 # theta deg angle between vec shaft & arrow hypot leg
```

This parameter is ignored when character arrowheads have been specified.

FIGURE 9. Line arrowhead parameters

2.1.22 Scarro parameter

The *scarro* parameter is the height of the line arrowhead. The value of this parameter is defined as a percentage derived by the ratio between the triangle height of the arrowhead and the vector length. To specify an arrowhead half as big as the vector length, for example, the *scarro* parameter would be fifty percent (50). The *scarro* parameter is of type integer. See Figure 9, on page 17, for an illustration of the line arrowhead parameters. Note the following example:

```
15 # scarro arrow len (triangle height) is % of vec shft
```

This parameter is ignored when character arrowheads have been specified.

2.1.23 Shfmin parameter

The *shfmin* parameter is the minimum vector length to draw line arrowheads. Line arrowheads will not be drawn on vectors that have a shorter length than the *shfmin* parameter. See Figure 9, on page 17 for an illustration of the line arrowhead parameters. The *shfmin* parameter is of type float. Note the following example:

```
0.2 # shfmin minimum shaft size for arrowheads
```

This parameter is ignored when character arrowheads have been specified.

2.1.24 Altchr parameter

The *altchr* parameter is a three way toggle that specifies the arrow head type. The *altchr* parameter is of type integer. Note the following example:

```
0 # altchr (-1) line arrow (0) norm char (1) extend char
```

If the value of the *altchr* parameter is negative one (-1), line arrowheads will be drawn. See Figure 18, on page 27 for an example vector field with line arrowheads.

If the value of the *altchr* parameter is zero (0), normal character (single stroke) arrowheads will be drawn and **vectum** will use the character specified by the *arvchr* parameter (see Section 2.1.25, on page 22).

If the value of the *altchr* parameter is one (1), high quality character (i.e. double stroke) arrowheads will be drawn and **vectum** will use the character specified by the *arvchr* parameter (see Section 2.1.25, on page 22). This option also allows an extended character set to be used for arrowheads. The extended character set lets the user take advantage of

numerous symbols. See Figures 10-13, on pages 19 and 22 for a display of the symbols available.

FIGURE 10. Alternate character set

PLCHHQ - COMPLEX CHARACTER SET

FUNCTION CODES SPECIFYING SIZE, FONT, AND CASE
 PRU PRL IRU IRL KRU KRL PGU PGL IGU IGL EGU EGL
 {0000} {0100} {0200} {0300} {0400} {0500} {0600} {0700} {0800} {0900} {1000} {1100} {1200} {1300}

STANDARD FONT RANS CHARACTERS	A (01)	A	a	A	a	A	Ⓐ	A	α	A	α	A	α
	B (02)	B	b	B	b	B	ℬ	B	β	B	β	B	β
	C (03)	C	c	C	c	C	ℭ	Γ	γ	Γ	γ	Γ	γ
	D (04)	D	d	D	d	D	ℰ	Δ	δ	Δ	δ	Δ	δ
	E (05)	E	e	E	e	E	ℰ	E	ε	E	ε	E	ε
	F (06)	F	f	F	f	F	ℱ	Z	ζ	Z	ζ	Z	ζ
	G (07)	G	g	G	g	G	⊕	H	η	H	η	H	η
	H (10)	H	h	H	h	H	⊗	Θ	θ	Θ	θ	Θ	θ
	I (11)	I	i	I	i	I	—	I	ι	I	ι	I	ι
	J (12)	J	j	J	j	J	/	K	κ	K	κ	K	κ
	K (13)	K	k	K	k	K		Λ	λ	Λ	λ	Λ	λ
	L (14)	L	l	L	l	L	\	M	μ	M	μ	M	μ

FIGURE 11. Alternate character set (cont.)

PLCHHQ — COMPLEX CHARACTER SET													
FUNCTION CODES SPECIFYING SIZE, FONT, AND CASE													
	PRU (0000)	PRL (0100)	IRU (0200)	IRL (0300)	KRU (0400)	KRL (0500)	PGU (0600)	PGL (0700)	IGU (1000)	IGL (1100)	KGU (1200)	KGL (1300)	
S T A N D A R D	M (15)	M	m	M	m	M	—	N	ν	N	ν	N	ν
	N (16)	N	n	N	n	N	/	Ξ	ξ	Ξ	ξ	Ξ	ξ
	O (17)	O	o	O	o	O	/	O	o	O	o	O	o
F O R T R A N	P (20)	P	p	P	p	P		Π	π	Π	π	Π	π
	Q (21)	Q	q	Q	q	Q	\	P	ρ	P	ρ	P	ρ
	R (22)	R	r	R	r	R	/	Σ	σ	Σ	σ	Σ	σ
C H A R A C T E R S	S (23)	S	s	S	s	S	-	T	τ	T	τ	T	τ
	T (24)	T	t	T	t	T	.	Υ	υ	Υ	υ	Υ	υ
	U (25)	U	u	U	u	U	!	Φ	φ	Φ	φ	Φ	φ
	V (26)	V	v	V	v	V	~	X	χ	X	χ	X	χ
	W (27)	W	w	W	w	W	o	Ψ	ψ	Ψ	ψ	Ψ	ψ
	X (30)	X	x	X	x	X	□	Ω	ω	Ω	ω	Ω	ω

FIGURE 12. Alternate character set (cont.)

PLCHHQ – COMPLEX CHARACTER SET												
FUNCTION CODES SPECIFYING SIZE, FONT, AND CASE												
	PRU (0000)	PRL (0100)	IRU (0200)	IRL (0300)	KRU (0400)	KRL (0500)	PGU (0600)	PGL (0700)	IGU (1000)	IGL (1100)	KGU (1200)	KGL (1300)
STANDARD	Y (31)	Y	y	Y	y	Y	Δ	○	○	○	○	○
	Z (32)	Z	z	Z	z	z	◇	○	○	5	~	R
	0 (33)	0	:	0	:	0	:	0	→	0	→	0
	1 (34)	1	;	1	;	1	;	1	↑	1	↑	1
FORTRAN	2 (35)	2	!	2	!	2	!	2	←	2	←	2
	3 (36)	3	?	3	?	3	?	3	↓	3	↓	3
	4 (37)	4	×	4	×	4	×	4	'	4	'	4
	5 (40)	5	.	5	.	5	.	5	'	5	'	5
CHARACTERS	6 (41)	6	÷	6	÷	6	□	6	'	6	'	6
	7 (42)	7	≡	7	≡	7		7	'	7	'	7
	8 (43)	8	<	8	<	8	⊥	8	'	8	'	8
	9 (44)	9	>	9	>	9	∠	9	"	9	"	9

FIGURE 13. Alternate character set (cont.)

PLCHHQ – COMPLEX CHARACTER SET													
FUNCTION CODES SPECIFYING SIZE, FONT, AND CASE													
	PRU (0000)	PRL (0100)	IRU (0200)	IRL (0300)	KRU (0400)	KRL (0500)	PGU (0800)	PGL (0700)	IGU (1000)	IGL (1100)	KGU (1200)	KGL (1300)	
STANDARD FORTRAN CHARACTERS	+(45)	+	$\leq$	+	$\leq$	+	$\therefore$	&	#	&	#	•	#
	-(46)	—	$\geq$	—	$\geq$	—	☆	⊂	⊃	⊂	⊃	■	┌
	*(47)	*	∂	*	∂	*	▽	∪		∪		▲	∧
	/(50)	/	∇	/	∇	/	∇	⊃		⊃		◀	
	((51)	(	[	(	[	<	{	⌈	⌋	⌈	⌋	<	{
	) (52)	)	]	)	]	>	}	⌋	⌈	⌋	⌈	>	}
	\$(53)	\$	✓	\$	✓	\$	Y	⊂	≠	⊂	≠	▼	✓
	=(54)	=	∫	=	∫	=	∫	∈	∅	∈	∅	▷	∫
	(55)												
	, (56)	,	∞	,	∞	,	∞	∞	±	∞	±	★	≡
	. (57)	.	%	.	%	.	°	~	≠	~	≠	▶	---

2.1.25 Arwchr parameter

The *arwchr* parameter specifies the arrowhead character. The *arwchr* parameter is of type character string. Note the following example:

```
'v'      # arwchr      arrowhead character
```

The type of arrowhead displayed will depend upon the value of the *altchr* parameter (see Section 2.1.24, on page 18). If normal character type is specified by *altchr* parameter, an arrowhead with a single stroke character will be drawn. If extended character type is specified by *altchr* parameter, double stroke characters with serifs will be used for the arrowheads.

The extended character set allows the user to take advantage of numerous symbols. See Figures 10-13, on pages 19 and 22 for a display of the symbols available.

To use an alternate character symbol, observe the following procedure:

1. Locate the desired symbol from Figures 10-13.
2. Determine the symbol's three character *function code family* as indicated at the top of the column that the symbol is contained in.
3. Prefix the function code with the grave symbol (').
4. Determine the symbol's one character *standard fortran character family* as indicated at the left side of the row that the symbol is contained in.
5. Prefix the standard fortran character with the grave symbol (').
6. Concatenate the function code family and the fortran character family.

To specify a double dagger ($\ddagger$) symbol for the arrowhead character, you would use 'KRL for the function code family and 'D for the standard fortran character family or 'KRL'D

If more than one symbol from the *same* function code family (or same column) is used, the function code should be specified only once. In addition, the prefixed grave symbol (') can apply to multiple entries from the fortran character family. The following string is an example of how multiple symbols from the same function code family would be specified:

```
'PGL'ABCDEFGHIJKLMNPOQRSTUVWXYZ
```

This string would generate the symbols as displayed in Figure 14.

FIGURE 14. Characters in the same function code family

If symbols from *different* function code families are used, the function code should be specified each time. The following string is an example of how symbols from different function

code families would be specified:

```
'PRU' - 'PRL' - 'IRU' - 'IRL' - 'KRU' - 'KRL' - 'PGU' - 'PGL' -
```

This string would generate the symbols as displayed in Figure 15.

FIGURE 15. Characters in differing function code families

Alternate character symbols can also be used in the plot *title* (see Section 2.1.4, on page 5, regarding the “*Title parameter*”) and are specified in the same manner.

2.1.26 Arwsiz parameter

The *arwsiz* parameter controls the maximum size of the arrowhead character (see Section 2.1.25, on page 22, regarding the “*Arwchr parameter*”). The *arwsiz* parameter is of type integer. Note the following example:

```
20    # arwsiz      maximum arrowhead size
```

Each arrowhead character is drawn at the size specified by this parameter when the *useshf* parameter (see Section 2.1.28, on page 25) is set to display a constant arrowhead size.

When the *arwsiz* parameter is set to display variable arrowhead size (i.e. no vector shaft), the size of the each arrowhead character is dependant upon the magnitude of it's u/v value. The arrowhead characters are scaled from the smallest character size to the size specified by this parameter. The range of the *arwsiz* parameter is from 3 to 24.

2.1.27 Arwang parameter

The *arwang* parameter is the angle of the arrowhead character (see Section 2.1.25, on page 22, regarding the “*Arwchr parameter*”). The *arwang* parameter is of type integer. Note the following example:

```
0    # arwang      arrowhead angle
```

The range of the *arwang* parameter is from 0 to 360. If the angle is set to zero, the arrowhead character is usually oriented to the vector shaft appropriately.

2.1.28 Useshf parameter

The *useshf* parameter is a three way toggle for controlling the arrowhead scaling and turning the vector shaft on and off. The *useshf* parameter is of type integer. Note the following example:

```
1 # useshf      (-1) scatter      (0) no shaft      (1) use shaft
```

If the value of the *useshf* parameter is negative one (-1), the vector shaft will *not* be displayed and the arrowhead (or marker) size will *not* be scaled in proportion to the u/v values. Instead, each arrowhead will be a constant value as specified by the *arwsiz* parameter (see Section 2.1.26, on page 24). See Figure 16 for a scatter plot with a constant marker size.

FIGURE 16. Scatter plot with a constant marker size

If the value of the *useshf* parameter is zero (0), the vector shaft will *not* be displayed and the arrowhead (or marker) size will be scaled in proportion to the u/v values. See Figure 17 for a scatter plot with a variable marker size.

FIGURE 17. Scatter plot with a variable marker size

If the value of the *useshf* parameter is one (1), the vector shaft will be displayed and the arrowhead size will be scaled in proportion to the u/v values.

2.1.29 Decinc parameter

The *decinc* parameter is the decimation increment value. This parameter can be used to

reduce the number of dataset values that are displayed. The *decinc* parameter is of type integer. Note the following example:

```
1 # decinc decimation. if (decinc = 1) no values skipped
```

The *decinc* parameter decimates the data values while they are being read from the data file into **vectum**.

If the value of the *decinc* parameter is one (1), **vectum** will read every data value (see Figure 18).

FIGURE 18. Line arrowheads with decimation factor of 1

If the parameter is five (5), for example, every fifth value will be read (see Figure 19). The *decinc* parameter is used internally in modulus division to determine even multiples of the dataset values to be displayed.

FIGURE 19. Line arrowheads with decimation factor of 5

FIGURE 20. Specifying a range using a logical operator

2.1.30 Vecmin parameter

The *vecmin* parameter is the value of the minimum vector length displayed. The *vecmin* parameter is of type float. Note the following example:

```
0.0 # vecmin      minimum vector length displayed
```

This parameter works in conjunction with the *optmin* parameter (see Section 2.1.31). If the user wanted to display only those vectors with a length greater than zero, for example, the *vecmin* parameter would be zero (0.0) and the *optmin* parameter would be the **greater than** ('>') logical operator. See Figure 23, on page 32 for an illustration specifying a maximum range with the *vecmin* and *optmin* parameter.

2.1.31 Optmin parameter

The *optmin* parameter uses a logical operator to specify the minimum range of vectors displayed. The *optmin* parameter is of type character string. Note the following example:

```
'?' # optmin      display vec (<, >, <=, >=, ==, ?) min len
```

If the *optmin* parameter is the **less than** ('<') logical operator, only vector lengths less than (but not including) the value specified by the *vecmin* parameter will be displayed.

If the *optmin* parameter is the **greater than** ('>') logical operator, only vector lengths greater than (but not including) the value specified by the *vecmin* parameter will be displayed.

If the *optmin* parameter is the **less than or equal to** ('<=') logical operator, only vector lengths less than the value specified by the *vecmin* parameter will be displayed. This logical operator also *includes* the *vecmin* value itself in the range.

If the *optmin* parameter is the **greater than or equal to** ('>=') logical operator, only vector lengths greater than the value specified by the *vecmin* parameter will be displayed. This logical operator also *includes* the *vecmin* value itself in the range.

If the *optmin* parameter is the **equal to** ('==') logical operator, only vector lengths equal to the value specified by the *vecmin* parameter will be displayed.

If the *optmin* parameter is a **question mark** ('?') symbol, the *vecmin* parameter is ignored.

See Figure 20, on page 29 for an illustration that shows using the logical operators to specify a range.

2.1.32 Vecmax parameter

The *vecmax* parameter is the value of the maximum vector length displayed. The *vecmax* parameter is of type float. Note the following example:

```
0.0      # vecmax      maximum vector length displayed
```

This parameter works in conjunction with the *optmax* parameter (see Section 2.1.33). If the user wanted to display only those vectors with a length less than twenty-one hundred, for example, the *vecmax* parameter would be twenty-one hundred (2100.0) and the *optmax* parameter would be the **less than** ('<') logical operator. See Figure 22, on page 32 for an illustration specifying a minimum range with the *vecmax* and *optmax* parameter.

2.1.33 Optmax parameter

The *optmax* parameter uses a logical operator to specify the maximum range of vectors displayed. The *optmax* parameter is of type character string. Note the following example:

```
'?'      # optmax      display vec (<, >, <=, >=, ==, ?) max len
```

If the *optmax* parameter is the **less than** ('<') logical operator, only vector lengths less than (but not including) the value specified by the *vecmax* parameter will be displayed.

If the *optmax* parameter is the **greater than** ('>') logical operator, only vector lengths greater than (but not including) the value specified by the *vecmax* parameter will be displayed.

If the *optmax* parameter is the **less than or equal to** ('<=') logical operator, only vector lengths less than the value specified by the *vecmax* parameter will be displayed. This logical operator also *includes* the *vecmax* value itself in the range.

If the *optmax* parameter is the **greater than or equal to** ('>=') logical operator, only vector lengths greater than the value specified by the *vecmax* parameter will be displayed. This logical operator also *includes* the *vecmax* value itself in the range.

If the *optmax* parameter is the **equal to** ('==') logical operator, only vector lengths equal to the value specified by the *vecmax* parameter will be displayed.

If the *optmax* parameter is a **question mark** ('?') symbol, the *vecmax* parameter is ignored.

See Figure 20, on page 29 for an illustration that shows using the logical operators to specify a range.

The *optmin* and *optmax* parameters can be used together to specify a finite range of displayed vectors. See Figure 21.

FIGURE 21. Finite range specified

FIGURE 22. Minimum range specified

FIGURE 23. Maximum range specified

The *optmin* and *optmax* parameters can also be used together to specify a infinite range of displayed vectors. See Figure 24.

FIGURE 24. Infinite range specified

2.1.34 Movie parameter

The *movie* parameter is a toggle that allows the user to specify multiple filenames on the command line and use multiple datasets to build a *movie* or merge several frames together. The *movie* parameter is of type integer. Note the following example:

```
1 # movie (0) merge multi frame (1) append multi frame
```

This parameter is not currently implemented.

2.2 Geometry database

Vectum also gives the user the capability to define simple, 2D geometry that is displayed with the vector field. The filename is specified by the *filgeo* parameter (see Section 2.1.8, on page 6) in the parameter file.

The format of the ASCII database and the geometry descriptors are described in Sections 2.2.1-2.2.6 on pages 36-41. The following is an example listing of a geometry database:

```
camas% cat geom.geo
'% database name: geom.geo
'% created by: Fred R. McLure, The TRP Society
'% creation date: March 11, 1991
```


[illegible]

```

'A' 20.0 30.0 10.0 45.0 315.0
'A' 30.0 20.0 10.0 225.0 135.0

'#' curve (spline) descriptor.
'#' format: 'C' start_x start_y
'#' 'C' absolute_x absolute_y
'#' .
'#' .
'#' .
'#' 'C' end_x end_y
'C' 5.000000 20.000000
'C' 8.888889 23.213938
'C' 12.777778 24.924019
'C' 16.666666 24.330127
'C' 20.555555 21.710101
'C' 24.444445 18.289899
'C' 28.333334 15.669873
'C' 32.222221 15.075961
'C' 36.111111 16.786062
'C' 40.000000 20.000000

```

Figure 25 is was generated using the geometry database listed above.

FIGURE 25. Miscellaneous geometry defined by the geometry database

2.2.1 Comment descriptor

Comment lines can be used in the geometry database to assist in documentation. Each record that begins with '#' denotes a comment. Any thing following the '#' is ignored. Note the following example:

```
'#' database name: geom.geo
'#' created by: Fred R. McClurg, the CRT Jockey
'#' creation date: March 11, 1991
'#' last modified: April 3, 1992
'#' group name: Technical Services, Visualization and Imaging (4120)
'#' email address: frm@inel.gov
'#' phone: (208) 526-9720
'#' office: ISC Building, Suite G-4
'#' mail stop: 2608

'#' purpose: A sample geometry description file.
```

2.2.2 Dash descriptor

The *dash descriptor* is used to change the line (or curve) style from a solid to a user specified pattern. A *dash descriptor* begins with 'D' and is followed by a character string enclosed in single quotes (' '). The character string specifies the dash pattern of the line style on all geometry defined after the *dash descriptor* is specified. Note the following example:

```
'#' dash descriptor.
'#' format: 'D' 'DASH PATTERN'
'D' '-----MY STRING-----'
```

Figure 26, on page 37 was generated by using several different *dash descriptors* in a geometry database and a vector field.

FIGURE 26. Geometry drawn using the dash descriptor

2.2.3 Line descriptor

The *line descriptor* defines a line by specifying end point coordinate values. A *line descriptor* begins with 'L' and is followed by four floating point values. Note the following example:

```
'# ' line descriptor.  
'# ' format: 'L' x1 y1 x2 y2  
'L' 5.0 5.0 20.0 5.0
```

The mesh displayed in Figure 27 was generated by using the *line descriptor*.

FIGURE 27. Triangular grid mesh drawn using the line descriptor¹

2.2.4 String descriptor

The *string descriptor* defines a string by specifying a start point coordinate values followed

1. This figure is an unstructured triangular grid of a staggered tube array. The grid was generated using GEN2D, a program written by Rainald Lohner, Navel Research Laboratory, Washington D.C., and grider, a program using the NCAR Graphics Library written by Vincent A. Mousseau, Idaho National Engineering Laboratory, Idaho Falls, ID.

My thanks go to Michael Stewart, Idaho National Engineering Laboratory, Idaho Falls, ID, for this contribution.

by one or more connecting coordinate values. After the starting point is specified, the following coordinates can be thought of as “pen down” positions. A *string descriptor* begins with 's' and is followed by two floating point values. Note the following example:

```
'#' string descriptor.
'#' format: 'S' start_x start_y
'#' 'S' absolute_x absolute_y
'#' .
'#' .
'#' .
'#' 'S' end_x end_y
'S' 5.0 40.0
.
.
'S' 5.0 35.0
'#'
```

The string is terminated (pen up mode) by specifying a descriptor other than the *string descriptor*, like the *comment*, for example. The continent outline in Figure 28 was generated by using the *string descriptor*.

FIGURE 28. Geometry drawn using the string descriptor

2.2.5 Arc (circle) descriptor

The *arc descriptor* (or *circle descriptor*) defines an arc by specifying the center point coordinate values, the arc radius and the start and end angle (in degrees). An *arc descriptor* begins with 'A' and is followed by five floating point values. Note the following example:

```
'#' arc (circle) descriptor.  
'#' format: 'A' ctr_x ctr_y radius start_angle end_angle  
'A' 20.0 30.0 10.0 45.0 315.0
```

Figure 29 was generated by using the *arc descriptor* with a vector field.

FIGURE 29. Geometry drawn using the arc (circle) descriptor²

2. This figure is a 2D simulation of a flow through a staggered tube array. Velocity vectors are shown indicating direction and magnitude of the flow field. This figure shows that the effects of flow blockage around a tube bundle, decreases the efficiency of a heat exchanger. Finite Volume Compressible Flow Solver software was used to generate the vector field.

My thanks go to Michael Stewart, Idaho National Engineering Laboratory, Idaho Falls, ID, for this contribution.

2.2.6 Curve (spline) descriptor

The *curve descriptor* (or *spline descriptor*) defines a spline by specifying the starting point coordinate values, followed by one or more connecting coordinate values. A *curve descriptor* begins with 'C' and is followed by two floating point values. Note the following example:

```
'#' curve (spline) descriptor.
'#' format: 'C' start_x start_y
'#' 'C' absolute_x absolute_y
'#' .
'#' .
'#' .
'#' 'C' end_x end_y
'C' 5.000000 20.000000
.
.
'C' 40.000000 20.000000
```

Figure 30 was generated by using the *curve descriptor*.

FIGURE 30. Geometry drawn using the curve (spline) descriptor

2.3 Vector database

The vector database gives the user the capability to define a regular, irregular, or random gridded vector field in an ASCII database. The filename is specified by the *filein* parameter (see Section 2.1.6, on page 6) in the parameter file.

Vectors are defined by specifying the x/y coordinate values and the u/v velocity component respectively. The format of the vector database is simply four floating point values on each line. The following is an example listing of a vector database:

```
camas% cat vector.dat
1.000000 2.000000 0.000000 0.000000
2.000000 3.000000 9.848078 1.736482
3.000000 4.000000 18.793852 6.840403
.
.
.
```

Figure 31 illustrates the individual parts of a velocity vector.

FIGURE 31. Coordinates of a velocity vector

3 Vectum Output

The output from **vectum** can be displayed on a monitor (computer screen), submitted to a default or networked printer, and/or can be used to generate several different file formats. The following is a brief discussion regarding the use of the NCAR utilities to manipulate the output.

3.1 Displaying to a monitor

Ctrans is a NCAR CGM translator. It can be used to display a NCAR CGM file to a terminal.

3.1.1 X11 driver

The command syntax for displaying a metafile to a 700x700 pixel, X11 window, positioned at the upper-left corner of the screen, is as follows:

```
host% ctrans -d X11 -geom 700x700+10+10 gmeta &
```

Setting the GRAPHCAP environment variable can eliminate the need for the "-d x11" device type switch on the **ctrans** command line. The FONTCAP can also be set with an environment variable. Note the following commands:

```
host% setenv GRAPHCAP X11
host% setenv FONTCAP font1
```

These commands can also be placed in the "~/.cshrc" or "~/.login" file and will be executed automatically upon login.

An entry can be placed in the applications defaults file to eliminate the need for the "-geom 700x700+10+10" geometry window specifier switch on the **ctrans** command line. The following entry should be placed in the "~/.xdefaults" file:

```
ctrans*geometry: 700x700+10+10
```

The X11 driver on **ctrans** also allows you to change the foreground and background colors. Note the following:

```
host% ctrans -d X11 -background pink \
        -foreground green gmeta &
```

A list of color names and their red, green, blue values are found in the

"/usr/lib/X11/rgb.txt" file.

3.1.2 Tektronix driver

Ctrans can also be used to display a NCAR metafile to a Tektronix 4115 terminal (or emulator). The command syntax is as follows:

```
host% ctrans -d t4115 gmeta &
```

The GRAPHCAP environment variable for a Tektronix 4115 terminal would be as follows:

```
host% setenv GRAPHCAP t4115
```

3.2 Submission to a printer

Besides displaying a NCAR CGM file, **ctrans** can be used to spool the file directly to a printer. Several output device drivers are available.

3.2.1 PostScript driver

The syntax for spooling to a monochrome PostScript printer is as follows:

```
host% ctrans -d ps.mono gmeta | lpr -Pprinter
```

The syntax for translating a CGM file to PostScript format and spooling it directly to the Imagen printer from the cray or jade is as follows:

```
jade% ctrans -d ps.mono gmeta | ipr -Pimagen \
-Lultrascript
```

If you get real creative, (and have the proper authorizations in the "~/rhosts" file) you can even spool a PostScript file to the Imagen from your own workstation. The following is an alias from a "~/cshrc" file:

```
alias pstoimagen 'ctrans -d ps.mono gmeta | rsh jade \
/usr/local/bin/ipr -Pimagen -Lultrascript'
```

3.2.2 Impress driver

The syntax for translating a CGM file to Impress format and spooling it directly to the Imagen printer from the cray or jade is as follows:

```
jade% ctrans -d imagen gmeta | ipr -Pimagen -Limpress
```

Again, with some Unix intuition, (and the proper authorizations in the “`~/.rhosts`” file) you can spool an Impress file to the Imagen from your own workstation. The following is an alias from a “`~/.cshrc`” file:

```
alias imptoimagen 'ctrans -d imagen gmeta | rsh jade \
    /usr/local/bin/ipr -Pimagen -Limpress'
```

3.2.3 HPLJ driver

Ftrans is also a NCAR CGM translator. NCAR currently recommends that you use the utilities **ctrans**, **ietrans**, or **idt** in every case *except* when plotting to HP LaserJet printers. The syntax for spooling to a HP LaserJet printer is as follows:

```
host% ftrans -d hplj300p gmeta | lpr -Pprinter
```

3.3 Generating a file

Ctrans can also be used to translate the CGM file into several file formats. The file can then be transferred across the network to another workstation or be imported into a desktop publishing package (like this one³).

3.3.1 PostScript file

Ctrans can be used to translate the CGM file into a PostScript file. The syntax for creating a monochrome PostScript file is as follows:

```
host% ctrans -d ps.mono gmeta > gmeta.ps
```

3.3.2 XWD file

Ctrans can be used to translate the CGM file into X Window Dump (XWD) format. The syntax for creating a XWD file is as follows:

```
host% ctrans -d xwd -resolution 900x900 gmeta > \
    gmeta.xwd
```

3. This documentation was generated using FrameMaker[®] Version 3.1X by Frame Technology Corp.

Note that the resolution of the image can be specified by using the “-resolution” command line switch.

3.3.3 Sun Raster file

Ctrans can be used to translate the CGM file into Sun Raster format. The syntax for creating a Sun Raster file is as follows:

```
host% ctrans -d sun -resolution 900x900 gmeta > \
      gmeta.rs
```

Note that the resolution of the image can be specified by using the “-resolution” command line switch.

Before importing raster output from **vectum** into a desk-top publishing package, you may wish to force the image to monochrome and then invert black for white. This will force the background to white and the foreground (i.e. vectors, axes, labels) to black. This can be done using Jef Poskanzer's portable pixmap (ppm), portable graymap (pgm), and portable bitmap (pbm) utilities (available by anonFTP on jade as “pub/src/utills/pbmplus.tar.z”). Note the following:

```
host% ctrans -d sun -resolution 900x900 gmeta | \
      rasttopnm | ppmtopgm | pgmtopbm | pnminvert | \
      pnmtorast > gmeta.rs
```

The Figure 32 was generated by using the *pbmplus utilities* with a Sun Raster file and imported into this document. See Figure 32, on page 46 for a comparison with an imported Encapsulated PostScript file.

FIGURE 32. Imported Sun Raster file

3.3.4 Encapsulated PostScript file

NCAR does not have an Encapsulated PostScript driver for **ctrans**, however, PostScript can be converted into Encapsulated PostScript without great loss of resolution. First, generate a PostScript file:

```
host% ctrans -d ps.mono gmeta > gmeta.ps
```

Then, convert the PostScript file to Encapsulated PostScript by using the utility **pstoepsi** (available by anonFTP on jade as "pub/src/utils/pstoepsi.tar.gz"). The "-news" switch on **pstoepsi** uses Sun's *X/NeWS* (OpenWindows) PostScript interpreter to perform the conversion:

```
host% pstoepsi -news -strip qmeta.ps qmeta.eps
```

If *X/NeWS* is not available, the PostScript file can be rasterized using *ghostscript* (available by anonFTP on jade as "pub/src/utils/ghostscript*.tar.gz"), a public domain PostScript interpreter. The "-gs" switch on **pstoepsi** uses *ghostscript* to perform the conversion.

```
host% pstoepsi -gs -strip qmeta.ps qmeta.eps
```

The Figure 33 was generated using the "-news" switch on the **pstoepsi** command and imported into this document. See Figure 32, on page 46 for a comparison with an imported raster file.

FIGURE 33. Imported Encapsulated PostScript file

Vectum User's Guide

References

Adobe Systems, Inc., 1987, *Encapsulated PostScript File Format Version 1.2*, Mountain View, California

ANSI/ISO, 1990, "Computer Graphics Metafile", ANSI/ISO, American National Standards Institute/International Standards Organization, ISO 8632 PT 1, 2, 3, and 4-90 (Revision of ANSI X3.122-1986).

Clare, F., Kennison, D., and Lackman, B., 1987, *NCAR Graphics User's Guide, Version 2.00*, Boulder, Colorado: National Center For Atmospheric Research, Scientific Computing Division.

Clare, F., and Kennison, D., 1989, *NCAR Graphics Guide to New Utilities, Version 3.00*, Boulder, Colorado: National Center For Atmospheric Research, Scientific Computing Division.

Frame Technology Corporation, 1990, *FrameMaker Reference*, San Jose, California

Frame Technology Corporation, 1990, *Using FrameMaker*, San Jose, California

Massachusetts Institute Technology X Consortium, 1986, "X Window Dump File Format", XWDFile.h, Cambridge, Massachusetts

Poskanzer, J., 1991, "pnm, ppm, pgm, pbm", *UNIX Man Pages*, jet@well.sf.ca.us

Sobell, M., 1989, *A Practical Guide to the UNIX System*, 2nd ed., Redwood City, California: Benjamin/Cummings Publishing Company, Inc.

Sun Microsystems, Inc., 1987, "rasterfile", *UNIX Man Pages*, Mountain View, California

Taft, E., and Walden, J., Adobe Systems, Inc., 1990, *PostScript Language Reference Manual*, 2nd ed., Reading, Massachusetts: Addison-Wesley Publishing Company.

Glossary

- alias:** A mechanism in the C and Korn Shells that permits the definition of new commands.
- ASCII:** Acronym that stands for the American National Standard Code for Information Interchange. It uses seven bits to represent letters, numbers, punctuation and control characters. ASCII is one of the most common human-readable, file formats and is used for program source code and when exchanging information between computers.
- cat:** Unix command to concatenate or display files.
- cd:** Unix command to change working directory.
- CGM:** Acronym that stands for Computer Graphics Metafile. CGM is a standard file format defined by ANSI X3.122-1986.
- .cshrc:** A command file in the home directory that the C Shell executes each time a new shell is invoked. This file is used for establishing variables and aliases.
- ctrans:** A NCAR Graphics utility for translating a NCAR CGM file. It can be used to display the CGM file to a terminal, spool the file directly to a printer, or convert the file into one of several file formats.
- default.vec:** An ASCII database in the present working directory that is read by the program **vectum** and affects how the program is executed. The file contains parameter information that controls details of the displayed vector field.
- Encapsulated PostScript:** A variation of the PostScript file format that includes a bounding box.
- f77:** Unix command to access the FORTRAN 77 compiler.
- Finite Volume Compressible Flow Solver:** A program that solves finite volume compressible flow problems.
- FrameMaker:** A commercial, What-I-See-Is-What-I-Get (WISIWIG) desktop publishing package by Frame Technology Corp., San Jose, CA. FrameMaker generates publication-quality documentation through a motif-like, point-and-click user interface.
- ftp:** Acronym that stands for File Transfer Protocol. FTP is used to transfer files from one machine on the network to another.
- fttrans:** A NCAR Graphics utility for translating a NCAR CGM file to a HP LaserJet printer.
- GEN2D:** A program for generating an unstructured triangular grid mesh, written by Rainald Lohner, Navel Research Laboratory, Washington D.C.
- ghostscript:** A public domain PostScript previewer (and interpreter).
- gmeta:** The default CGM output filename generated by **vectum** and several other NCAR Graphics utilities.
- grider:** A program for generating an unstructured triangular grid mesh, based on the NCAR Graphics Library and written by Vincent A. Mousseau, Idaho National Engineering Laboratory, Idaho Falls, ID.

- ictrans:** A command-driven, interactive NCAR Graphics utility for translating a NCAR CGM file.
- idt:** An X-based, point-and-click, interactive NCAR Graphics utility for translating a NCAR CGM file.
- INEL:** Acronym that stands for Idaho National Engineering Laboratory.
- lpr:** Unix command to queue file(s) to an Imagen printer.
- .login:** A command file in the home directory that the C Shell executes each time the user logs in or gains access to a Unix system by responding correctly to the login and password prompt. This file is used to set environment variables and run commands that are executed at the beginning of each login session.
- lpr:** Unix command to queue file(s) to a network printer.
- ls:** Unix command to display information about one or more files.
- make:** Unix utility to update files. The make utility is most often used to compile and link a set of program source files.
- makefile:** An ASCII database, used by the make utility, that contains Unix commands and defines file relationships.
- mkdir:** Unix command to make a directory.
- NCAR:** Acronym that stands for the National Center for Atmospheric Research, an organization located in Boulder, Colorado.
- pbmplus:** A set of public domain utilities (filters) written by Jef Poskanzer for converting and modifying raster images.
- PostScript:** The popular file format written by Adobe Systems, Inc., Mountain View, CA.
- pstoepsi:** A public domain script for converting an arbitrary PostScript image to an Encapsulated PostScript image with a bitmap, suitable for incorporation into FrameMaker, LaTeX, troff, etc.
- pwd:** Unix command to display pathname of the current working directory.
- rgb.txt:** The ASCII database that assigns names to red, green, blue, values. Those names can then be used by many X-based programs.
- .rhosts:** The ASCII database in the home directory for specifying remote hosts and users that are considered *trusted*. This file is used by several Unix programs (like **rcp**, **rsh**, and **rlogin**) to bypass the standard password-based user authentication mechanism.
- rm:** Unix command to remove a file(s).
- rsh:** Unix command to execute a shell (or command) remotely on another machine.
- setenv:** Unix command setting an environment variable.
- Sun Raster:** Sun's file format for raster images.
- tar:** Unix command for storing or retrieving files from an archive file or tape.
- vectum:** An easy to use, flexible, multi-purpose, 2D velocity vector plotting package based on the NCAR Graphics libraries, written by Fred R. McClurg and Vincent A. Mousseau, Idaho National Engineering Laboratory, Idaho Falls, ID.
- .Xdefaults:** The ASCII database that allows a user to customize an X application without recompiling.

XWD: Acronym that stands for X Window Dump. XWD is a popular raster file format among user's of the X11 windowing environment.

zcat: Unix command that reads a compressed file and generates uncompressed output while leaving the original file intact. **Zcat** eliminates the need to uncompress (and later compress) a file while extracting files from a compressed tarfile, for example.

**DATE
FILMED**

8/25/92